



Myra DataHub

SOC Manual (Cloud)

Version History

Version	Date	Reason for Change
V1.16	08/2026	Updated sections: • Networks view • Anomaly history view • Notifications tab • Edit company • Login
V1.15	08/2026	Updated sections: • Overview of the Myra DataHub portal • Company accounts view • Edit company • Networks view • Add Network • Edit network • View network • Delete network • Start manual mitigations • Stop manual mitigations • Mitigation history view • Mitigation reports view • Traffic Reports view • Company management • Dashboard view New sections: • Anomaly history view • Notifications tab • Listing all anomalies of the organisation • Changing the notification preference of the authenticated user • Adding a notification address to the organisation • Deleting a notification address from the organisation

Version	Date	Reason for Change
		• Manual as PDF
		Minor corrections
V1.14	07/2026	Minor corrections
V1.13	06/2026	New sections: • API tokens tab
V1.12	06/2026	Updated sections: • Network view • Add Network • Edit network • View network
V1.11	04/2026	Minor corrections
V1.10	03/2026	New sections: • Traffic Reports
		Minor corrections
V1.9	03/2026	Updated sections due to a new Details description field: • View network • Add Network
V1.8	02/2026	Minor corrections
V1.7	12/2025	New sections: • SIEM Settings tab
V1.6	11/2025	New layout
V1.5	09/2025	Updated sections for SIEM: • Add Company • Edit company
V1.4	08/2025	Updated sections: • Monthly Mitigation Report

Version	Date	Reason for Change
V1.3	07/2025	Minor corrections
V1.2	05/2025	Updated sections: • Overview of the Myra DataHub portal • View Business Management New sections: • Add Company • Edit company • Delete company • Add Network • Edit network • Delete network • Report view • Audit log view • View changelog
V1.1	04/2025	Minor corrections
V1.0	03/2025	Initial release

Contents

1. Myra DataHub	16
1.1 Description	16
1.1.1 What is the Myra DataHub?	16
1.2 Getting Started	17
1.2.1 Registration	17
1.3 DataHub portal	18
1.3.1 Overview of the Myra DataHub portal	18
1.3.1.1 Company accounts view	19
1.3.1.1.1 Edit company	21
1.3.1.2 Report view	24
1.3.1.2.1 Monthly Mitigation Report	25
1.3.1.3 Audit log view	26
1.3.1.4 Version history view	27
1.3.2 Company management	29
1.3.2.1 Dashboard view	31
1.3.2.2 Networks view	33
1.3.2.2.1 View network	35
1.3.2.2.2 Add Network	38
1.3.2.2.3 Edit network	40
1.3.2.2.4 Delete network	41
1.3.2.2.5 Start manual mitigations	42
1.3.2.2.6 Stop manual mitigations	44
1.3.2.3 Mitigation history view	45
1.3.2.3.1 Open mitigation reports	46
1.3.2.3.2 Mitigation reports view	46
1.3.2.4 Anomaly history view	48
1.3.2.4.1 Anomaly details dialog	50
1.3.2.5 Traffic Reports view	51
1.3.2.6 Audit log view	52

1.3.3 Company management	54
1.3.3.1 Company management view	55
1.3.3.2 User management tab	55
1.3.3.2.1 Add account	57
1.3.3.2.2 Change account	58
1.3.3.3 SIEM Settings tab	59
1.3.3.4 Notifications tab	61
1.3.3.4.1 Notifications area	61
1.3.3.4.2 Additional contacts area	62
1.3.4 Profile	64
1.3.4.1 Profile tab	64
1.3.4.1.1 Change username	65
1.3.4.1.2 Close active web browser sessions	65
1.3.4.2 Notifications tab	66
1.3.4.3 API tokens tab	67
1.3.4.3.1 Create API token area	67
1.3.4.3.2 Manage API tokens area	68
1.4 Permissions	70
1.4.1 Roles and permissions	70
2. API	73
2.1 Using the Myra API	73
2.2 General	74
2.2.1 Getting access to the Myra API	74
2.2.2 Authentication using bearer tokens	75
2.2.2.1 Creating API token	75
2.2.2.2 Request to the API using a bearer token	76
2.2.3 Used API methods	78
2.2.4 Possible responses to a request	79
2.2.4.1 Possible status codes	79
2.2.4.2 Objects used	79

2.3 API endpoints	81
2.3.1 Organisation management	82
2.3.1.1 Deleting an organisation	82
2.3.1.1.1 Description	82
2.3.1.1.2 Requirements	82
2.3.1.1.3 Request	82
2.3.1.1.4 Responses	83
2.3.1.2 Deleting the SIEM configuration of an organisation	83
2.3.1.2.1 Description	83
2.3.1.2.2 Requirements	83
2.3.1.2.3 Request	83
2.3.1.2.4 Responses	84
2.3.1.3 Listing organisations with network and mitigation details	84
2.3.1.3.1 Description	84
2.3.1.3.2 Requirements	84
2.3.1.3.3 Request	84
2.3.1.3.4 Example	85
2.3.1.3.5 Responses	87
2.3.1.4 Listing all organisations of the user	87
2.3.1.4.1 Description	87
2.3.1.4.2 Requirements	87
2.3.1.4.3 Request	87
2.3.1.4.4 Example	88
2.3.1.4.5 Responses	89
2.3.1.5 Getting an organisation by ID	89
2.3.1.5.1 Description	89
2.3.1.5.2 Requirements	89
2.3.1.5.3 Request	90
2.3.1.5.4 Example	90
2.3.1.5.5 Responses	91
2.3.1.6 Listing all mitigations of an organisation	92
2.3.1.6.1 Description	92
2.3.1.6.2 Requirements	92
2.3.1.6.3 Request	92
2.3.1.6.4 Example	94

2.3.1.6.5 Responses	96
2.3.1.7 Listing all networks of an organisation	96
2.3.1.7.1 Description	96
2.3.1.7.2 Requirements	96
2.3.1.7.3 Request	96
2.3.1.7.4 Example	98
2.3.1.7.5 Responses	99
2.3.1.8 Listing all users of an organisation	99
2.3.1.8.1 Description	100
2.3.1.8.2 Requirements	100
2.3.1.8.3 Request	100
2.3.1.8.4 Example	101
2.3.1.8.5 Responses	102
2.3.1.9 Changing the settings of an organisation	102
2.3.1.9.1 Description	102
2.3.1.9.2 Requirements	102
2.3.1.9.3 Request	102
2.3.1.9.4 Example	103
2.3.1.9.5 Responses	103
2.3.1.10 Changing the SIEM configuration of an organisation	104
2.3.1.10.1 Description	104
2.3.1.10.2 Requirements	104
2.3.1.10.3 Request	104
2.3.1.10.4 Example	106
2.3.1.10.5 Responses	106
2.3.1.11 Changing users within an organisation	106
2.3.1.11.1 Description	107
2.3.1.11.2 Requirements	107
2.3.1.11.3 Request	107
2.3.1.11.4 Example	108
2.3.1.11.5 Responses	108
2.3.1.12 Adding an organisation	109
2.3.1.12.1 Description	109
2.3.1.12.2 Requirements	109
2.3.1.12.3 Request	109
2.3.1.12.4 Example	110

2.3.1.12.5 Responses	110
2.3.1.13 Resending the confirmation email for a notification address	111
2.3.1.13.1 Description	111
2.3.1.13.2 Requirements	111
2.3.1.13.3 Request	111
2.3.1.13.4 Example	112
2.3.1.13.5 Responses	112
2.3.1.14 Adding users to the organisation	112
2.3.1.14.1 Description	113
2.3.1.14.2 Requirements	113
2.3.1.14.3 Request	113
2.3.1.14.4 Example	114
2.3.1.14.5 Responses	114
2.3.1.15 Removing a user from an organisation	114
2.3.1.15.1 Description	114
2.3.1.15.2 Requirements	115
2.3.1.15.3 Request	115
2.3.1.15.4 Example	115
2.3.1.15.5 Responses	116
2.3.1.16 Adding a notification address to the organisation	116
2.3.1.16.1 Description	116
2.3.1.16.2 Requirements	116
2.3.1.16.3 Request	117
2.3.1.16.4 Example	117
2.3.1.16.5 Responses	118
2.3.1.17 Deleting a notification address from the organisation	118
2.3.1.17.1 Description	118
2.3.1.17.2 Requirements	118
2.3.1.17.3 Request	119
2.3.1.17.4 Responses	119
2.3.2 Networks	120
2.3.2.1 Deleting a network from the organisation	120
2.3.2.1.1 Description	120
2.3.2.1.2 Requirements	120
2.3.2.1.3 Request	120
2.3.2.1.4 Responses	120

2.3.2.2 Listing all networks with their mitigation status	121
2.3.2.2.1 Description	121
2.3.2.2.2 Requirements	121
2.3.2.2.3 Request	121
2.3.2.2.4 Example	123
2.3.2.2.5 Responses	124
2.3.2.3 Listing all networks of the organisation	124
2.3.2.3.1 Description	124
2.3.2.3.2 Requirements	125
2.3.2.3.3 Request	125
2.3.2.3.4 Example	126
2.3.2.3.5 Responses	127
2.3.2.4 Getting a network by ID	128
2.3.2.4.1 Description	128
2.3.2.4.2 Requirements	128
2.3.2.4.3 Request	128
2.3.2.4.4 Example	130
2.3.2.4.5 Responses	131
2.3.2.5 Listing all mitigations of a network	131
2.3.2.5.1 Description	131
2.3.2.5.2 Requirements	131
2.3.2.5.3 Request	132
2.3.2.5.4 Example	133
2.3.2.5.5 Responses	135
2.3.2.6 Changing the settings of a network	135
2.3.2.6.1 Description	135
2.3.2.6.2 Requirements	136
2.3.2.6.3 Request	136
2.3.2.6.4 Example	140
2.3.2.6.5 Responses	141
2.3.2.7 Adding a network to the organisation	141
2.3.2.7.1 Description	141
2.3.2.7.2 Requirements	142
2.3.2.7.3 Request	142
2.3.2.7.4 Example	144
2.3.2.7.5 Responses	145

2.3.2.8 Starting a manual mitigation for a network	145
2.3.2.8.1 Description	146
2.3.2.8.2 Requirements	146
2.3.2.8.3 Request	146
2.3.2.8.4 Example	148
2.3.2.8.5 Responses	148
2.3.2.9 Stopping the active manual mitigation of a network	148
2.3.2.9.1 Description	149
2.3.2.9.2 Requirements	149
2.3.2.9.3 Request	149
2.3.2.9.4 Example	151
2.3.2.9.5 Responses	151
2.3.2.10 Triggering a resync of the networks of the organisation	152
2.3.2.10.1 Description	152
2.3.2.10.2 Requirements	152
2.3.2.10.3 Request	152
2.3.2.10.4 Responses	152
2.3.3 Mitigations	154
2.3.3.1 Listing all mitigations of the organisation	154
2.3.3.1.1 Description	154
2.3.3.1.2 Requirements	154
2.3.3.1.3 Request	154
2.3.3.1.4 Example	156
2.3.3.1.5 Responses	158
2.3.3.2 Getting a mitigation by ID	158
2.3.3.2.1 Description	158
2.3.3.2.2 Requirements	158
2.3.3.2.3 Request	159
2.3.3.2.4 Example	160
2.3.3.2.5 Responses	161
2.3.3.3 Getting graph data of a mitigation	161
2.3.3.3.1 Description	162
2.3.3.3.2 Requirements	162
2.3.3.3.3 Request	162
2.3.3.3.4 Example	162
2.3.3.3.5 Responses	163

2.3.3.4 Stopping a manual mitigation by ID	163
2.3.3.4.1 Description	163
2.3.3.4.2 Requirements	163
2.3.3.4.3 Request	163
2.3.3.4.4 Responses	165
2.3.4 Anomalies	166
2.3.4.1 Listing all anomalies of the organisation	166
2.3.4.1.1 Description	166
2.3.4.1.2 Requirements	166
2.3.4.1.3 Request	166
2.3.4.1.4 Example	168
2.3.4.1.5 Responses	169
2.3.5 Mitigation reports	170
2.3.5.1 Listing mitigation statistics for a month	170
2.3.5.1.1 Description	170
2.3.5.1.2 Requirements	170
2.3.5.1.3 Request	170
2.3.5.1.4 Example	171
2.3.5.1.5 Responses	172
2.3.5.2 Listing all months with mitigation statistics	173
2.3.5.2.1 Description	173
2.3.5.2.2 Requirements	173
2.3.5.2.3 Request	173
2.3.5.2.4 Example	174
2.3.5.2.5 Responses	174
2.3.6 Traffic Reports	175
2.3.6.1 Listing all months with traffic report data	175
2.3.6.1.1 Description	175
2.3.6.1.2 Requirements	175
2.3.6.1.3 Request	175
2.3.6.1.4 Example	176
2.3.6.1.5 Responses	176
2.3.6.2 Getting a traffic report for a type and period	176
2.3.6.2.1 Description	177
2.3.6.2.2 Requirements	177

2.3.6.2.3 Request	177
2.3.6.2.4 Example	178
2.3.6.2.5 Responses	179
2.3.7 Audit logs	180
2.3.7.1 Listing all audit log entries of the organisation	180
2.3.7.1.1 Description	180
2.3.7.1.2 Requirements	180
2.3.7.1.3 Request	180
2.3.7.1.4 Example	181
2.3.7.1.5 Responses	182
2.3.8 User management	183
2.3.8.1 Getting the account information of the authenticated user	183
2.3.8.1.1 Description	183
2.3.8.1.2 Requirements	183
2.3.8.1.3 Request	183
2.3.8.1.4 Example	183
2.3.8.1.5 Responses	184
2.3.8.2 Changing the notification preference of the authenticated user	184
2.3.8.2.1 Description	184
2.3.8.2.2 Requirements	184
2.3.8.2.3 Request	185
2.3.8.2.4 Example	185
2.3.8.2.5 Responses	186
3. Troubleshooting	187
3.1 Login	188
3.2 Access and display	192
3.3 Networks and mitigations	194
3.4 User accounts	196
3.5 Companies	198

3.6 API access	200
-----------------------	------------

4. Reference	202
---------------------	------------

4.1 Notational conventions	202
-----------------------------------	------------

4.2 Glossary	203
---------------------	------------

1. Myra DataHub

1.1 Description

1.1.1 What is the Myra DataHub?

Video: What is the Myra DataHub? – [playable in the online help](#)

The Myra DataHub is a web-based user interface for the Myra Flow Application that provides Myra partners with a better overview of their end customers.

For Myra partners, the user interface provides an overview of all end customers of a partner, including the connected networks, analyses, and mitigations as well as the accounts of the users. The partner can create, edit, and delete new customers as companies, and can add and manage networks and users of the organisation. End customers receive a clear presentation of their traffic history, a list of the activated networks, and the collected mitigation reports.

The traffic history contains a presentation of the bandwidth and the packet rate, sorted by destination IP and the packet rates by port, which can be displayed for various observation periods of up to 24 hours. In addition, the partner can use the user interface to view the configured thresholds and to start or stop a mitigation manually.

1.2 Getting Started

1.2.1 Registration

Proceed as follows to log in with your credentials:

- ▶ Log in to the Myra App, see the section Logging In Using Your Username and Password in the [Myra App manual](#) and the section Logging In Using Single Sign-On (SSO) in the [Myra App manual](#).
- ▶ Click on the **Network Security** tab.
- The **Dashboard** home page of the Myra DataHub opens.

1.3 DataHub portal

1.3.1 Overview of the Myra DataHub portal




Figure 1: Overview Home

After logging in, the **Dashboard** home page of the Myra DataHub appears.

On the home page, you can find the following information:

- Top menu bar with access to the following buttons (1):
 - Button with the company name for accessing user management
 - Button with flag icon for selecting the user interface language
 - Button with user profile picture for managing your own account settings
 - In the event of maintenance, important information about the type and duration will be shown here as a separate banner.
- Shows the content of the individual views (2)

■ Tabs with the following views (3):

-  Company
-  Report
-  Audit Log
-  Application Security for opening the Myra App
- Help & Support for opening the online help
- Display of the current version number, with the  icon for opening the **Changelog** view

1.3.1.1 Company accounts view

NAME	NETWORKS	MITIGATION STATUS	QUICK ACCESS
Muster GmbH	4	● Normal	                        

Element	Description
	Normal  : One or more mitigations have been successfully completed.
Quick Access	Shows the icons for direct access to the possible settings for the selected company.

The following options are available:

Element	Description
	The icon enables you to search specifically for names, customer IDs, and networks.
	The icon opens the Dashboard view of the respective company with information about its network traffic. See Dashboard view .
	The icon opens the Networks view of the respective company. Manual mitigations can be started or stopped immediately here. See Networks view .
	The icon opens the Mitigation history view of the respective company with a list of all past mitigations. See Mitigation history view .
	The icon opens the Audit Log view of the respective company with a list of all changes of the company. See Audit log view .
	The icon opens the Company management view of the respective company. Here you can view and change the settings for accounts. See User management view .
	The icon opens the Edit company dialog for editing the name and the settings of the company. See Edit company .
	To change a company, you need SOC administration rights.



In SOC mode, you act as the admin of the respective company. An orange status bar below the top navigation bar indicates that you are in SOC mode for a company.

If you have opened a company and want to return to the overview of all companies in the **Company accounts** view, you must use the **Back to the overview** button. Using the back button in the browser does not work.

If you initiate manual mitigation for a company or make other changes in SOC mode, this will be recorded in the audit logs as a change made by you as a SOC user.

You are in SOC mode for: Muster GmbH


Back to the overview

1.3.1.1.1 Edit company



To change a company, you need SOC administration rights.

Proceed as follows to change a company:




NAME	↑↓ NETWORKS	MITIGATION STATUS	↓ QUICK ACCESS
Muster GmbH	4	● Normal	✎ % 📄 📁 📧 📧 📧 📧 📧 📧
Beispiel AG	2	● Under mitigation	✎ % 📄 📁 📧 📧 📧 📧 📧 📧
Musterstadt Werke	6	● Normal	✎ % 📄 📁 📧 📧 📧 📧 📧 📧
Beispiel Handel KG	1	● Normal	✎ % 📄 📁 📧 📧 📧 📧 📧 📧

ITEMS PER PAGE: 10 | 1-4 OF 4 ITEMS

1 OF 1 PAGES

Figure 3: Button to edit a company

- Click on the  icon.
- ↳ The **Edit company** dialog opens.



The image shows a modal dialog box titled "Edit company" with a close button (X) in the top right corner. Inside the dialog, there is a section labeled "NAME" with a text input field containing "Muster GmbH". Below this, there are four checkboxes with corresponding labels: the first is checked and labeled "All users of this company can view and download mitigation reports."; the other three are unchecked and labeled "This company can use SIEM.", "This company can view and download traffic reports.", and "This company can use the anomaly and mitigation notifications feature.". At the bottom right of the dialog are two buttons: "Cancel" and "Save".

Figure 4: Edit company dialog

- ▶ Enter the new name of the company in the field under **Name**.
- ▶ If necessary, enable or disable the checkbox under **All users of this company can view and download mitigation reports..**



If the checkbox under **All users of this company can view and download mitigation reports.** is disabled, the users of the company can no longer view and download mitigation reports. This option cannot be enabled for individual users.

- If necessary, enable or disable the checkbox under **This company can use SIEM..**



SIEM (Security Information and Event Management) is a security solution that helps companies detect and respond to security threats. It collects, analyses, and correlates data from various sources to identify anomalies and potential security incidents. SIEM systems enable centralised monitoring and response to threats and help companies comply with compliance regulations.



The audit logs for SIEM integration are provided via a Splunk interface in JSON format and contain the following information:

- Start and stop events for mitigations
- Destination IP
- Measured packet rate (in PPS)
- Measured data rate (in bits/s)
- Configured thresholds for the IP address range
- User permissions (users and administrators)
- Mitigation reports

- If necessary, enable or disable the checkbox under **This company can view and download traffic reports..**



If the checkbox under **This company can view and download traffic reports.** is disabled, the users of the company can no longer view and download traffic reports. This option cannot be enabled for individual users.

- If necessary, enable or disable the checkbox under **This company can use the anomaly feature..**



If the checkbox under **This company can use the anomaly feature.** is enabled, the **Anomaly history** view is available to the users of the company and Myra also alerts them about traffic anomalies in addition to mitigations.


- Click on the **Save** button.
- A message confirms that the company has been successfully changed.

The changes are then also visible in the table in the **Company accounts** view.

1.3.1.2 Report view



The **Reports** view is only displayed for SOC administrators.



NAME	REPORT
Monthly Mitigation Report - May 2026	 
Monthly Mitigation Report - April 2026	 
Monthly Mitigation Report - March 2026	 
Monthly Mitigation Report - February 2026	 
Monthly Mitigation Report - January 2026	 
Monthly Mitigation Report - December 2025	 
Monthly Mitigation Report - November 2025	 
Monthly Mitigation Report - October 2025	 
Monthly Mitigation Report - September 2025	 
Monthly Mitigation Report - August 2025	 

ITEMS PER PAGE: 10 | 1-10 OF 10 ITEMS

1 OF 2 PAGES

Figure 5: Reports view

The **Reports** view provides access to the monthly reports on all started, successful, and cancelled mitigations of the individual companies.

The following information is available:

Element	Description
Name	The name, month, and year of the monthly report.
Report	Shows the icons for opening and downloading the monthly reports.

The following options are available:

Element	Description
	The icon opens the <report name> view for viewing the individual mitigation information.
	The icon allows you to download the complete monthly report as a CSV file.

1.3.1.2.1 Monthly Mitigation Report



NAME	NETWORK	STARTED	ENDED	BANDWIDTH THRESHOLD (MBit/s)	PACKET RATE THRESHOLD (PACKETS/s)	PEAK BANDWIDTH (MBit/s)	PEAK PACKET RATE (PACKETS/s)	DATA VOLUME (MBIT)	TOTAL PACKETS	DROPPED BYT (MBIT)	DROPPED PACKETS	MITIGATOR TYPE
Hoster GmbH	XXX.XXX.XXX.XXX/24	02.05.2020 11:04	02.05.2020 11:52	4,000 / 3,884	500,000 / 486,210	8,412	912,480	24,160,560	2,504,882,311	6,204,118	584,309,772	Automatic
Hoster GmbH	XXX.XXX.XXX.XXX/24	07.05.2020 03:18	07.05.2020 04:06	4,000 / 3,912	500,000 / 491,075	6,037	764,279	17,902,114	1,688,401,905	3,918,446	402,771,038	Automatic
Hoster GmbH	XXX.XXX.XXX.XXX/24	14.05.2020 20:41	14.05.2020 21:12	4,000 / 4,000	500,000 / 500,000	5,239	612,716	9,844,702	1,032,556,760	1,204,977	118,640,215	Manual
Hoster GmbH	XXX.XXX.XXX.XXX/48	21.05.2020 08:55	21.05.2020 09:47	10,000 / 9,760	800,000 / 782,640	12,806	1,204,311	38,412,907	3,818,229,664	11,882,503	1,096,884,310	Automatic
Hoster GmbH	XXX.XXX.XXX.XXX/24	28.05.2020 16:22	28.05.2020 16:58	4,000 / 4,000	500,000 / 500,000	4,760	528,903	10,288,415	1,147,330,028	902,315	94,336,507	Manual

Figure 6: Monthly Mitigation Report

The monthly report view provides you with detailed information about all mitigations that have been started, completed, and canceled for each company.

The following information is available:

Element	Description
Name	The name of the customer.
Network	The IP address of the network for which mitigation was initiated.
Started	The time and date when mitigation was initiated.
Ended	The time and date when the mitigation was completed.
Bandwidth Threshold (MBit/s)	The maximum bandwidth allowed for your network.
Packet Rate Threshold (Packets/s)	The maximum number of packets per second allowed on the network.

Element	Description
Peak Bandwidth (MBit/s)	The highest bandwidth utilization during mitigation.
Peak Packet Rate (Packets/s)	The highest number of packets per second during mitigation.
Data Volume (MBit)	The total data volume during mitigation.
Total Packets	The sum of all packets during mitigation.
Trigger type	Indicates whether mitigation was automatic or manual.

The following options are available:

Element	Description
	The symbol enables you to search specifically for the name of the report.
Download CSV	The Download button allows you to download the complete monthly report as a CSV file.

1.3.1.3 Audit log view

Audit Log

Download CSV

CREATED	COMPANY NAME	PERFORMED BY	EVENT	RESOURCE	RESOURCE ID	PARAMETERS
12.05.2026 09:14:22	Muster GmbH	max.mustermann@example.com	UPDATED	Network	XXX-XXX-XXX-XXX/24	bw_limit: 4000
12.05.2026 09:02:47	Muster GmbH	max.mustermann@example.com	CREATED	Network	XXX-XXX-XXX-XXX/24	pps_limit: 500000
11.05.2026 17:36:05	Beispiel AG	erika.musterfrau@example.com	UPDATED	User	erika.musterfrau@example.com	role: user
11.05.2026 16:20:31	Beispiel AG	erika.musterfrau@example.com	CREATED	User	jan.beispiel@example.com	role: admin
11.05.2026 14:58:12	Musterstadt Werke	jan.beispiel@example.com	DELETED	Network	XXXX-XXXX-XXXX-48	—
11.05.2026 11:41:09	Musterstadt Werke	jan.beispiel@example.com	UPDATED	Network	XXX-XXX-XXX-XXX/24	type: ACTION_BLACKHOLE
10.05.2026 18:07:53	Beispiel Handel KG	lena.sommer@example.com	CREATED	Company	10027	name: Beispiel Handel KG
10.05.2026 15:22:40	Muster Logistik SE	tobias.winter@example.com	UPDATED	Network	XXX-XXX-XXX-XXX/24	duration: 14400
10.05.2026 12:15:18	Muster Logistik SE	tobias.winter@example.com	DELETED	User	lena.sommer@example.com	—
09.05.2026 08:49:02	Beispiel Energie AG	max.mustermann@example.com	CREATED	Network	XXX-XXX-XXX-XXX/24	nettype: RIPE (P)
ITEMS PER PAGE: 10 1-10 OF 37 ITEMS						

1 OF 4 PAGES

Figure 7: Audit log view

In the **Audit Log** view, you can find detailed information about all changes made for your own company or your customers' companies.

The following information is available:

Element	Description
Created	The time and date when the change was made.
Company name	The name of the company.
Performed by	The name of the user.
Event	The type of the activity. CREATED : A new entry has been created. UPDATED : An existing entry has been modified. DELETED : An existing entry has been deleted.
Resource	The place of change.
Resource ID	The entry that has been changed.
Parameters	The values of the corresponding entry that have been changed.

The following options are available:

Element	Description
	The symbol filters the reports by names.
Download CSV	The button downloads the complete monthly report as a CSV file.

1.3.1.4 Version history view

The **Version history** view gives you access to an overview of all changes and adjustments in the individual versions of the Myra DataHub.

Proceed as follows to view the version history:

- ▶ Open the Myra DataHub.
- ▶ Log in.
 - ↳ The Myra DataHub home page with the company accounts opens.
- ▶ In the left menu bar, click on the name of the version or the  icon in the lower left corner.
- The **Version history** view opens.

The following information is shown:

- Name of the Myra DataHub version
- Date of publication
- Overview of individual adjustments and corrections

1.3.2 Company management

Proceed as follows to access a website of a company:

- ▶ Open the Myra App.
- ▶ Log in.
 - ↳ The Myra DataHub home page with the company accounts opens.
 - ↳ The home page of the Myra App opens.
- ▶ Click on the **Network Security** tab in the left navigation bar.
- ▶ Click on the name of the related company.
- The Myra DataHub home page with the company accounts opens.




Figure 8: Home page for companies

On the home page of each company, you can find the following information:

- Top menu bar with access to the following buttons (1):
 - Button with the company name for accessing user management
 - Button with flag icon for selecting the user interface language
 - Button with the user's profile picture for managing their own account settings
 - In the event of maintenance, important information about the type and duration will be shown here as a separate banner.
- Shows the content of the individual views (2)

■ Tabs with the following views (3):

-  Dashboard
-  Network
-  Mitigation history
- Anomaly history
-  Traffic Reports
-  Audit Log
-  Application Security for opening the Myra App
- Help & Support for opening the online help
- Display of the current version number with the  icon for opening the **Changelog** view (see [Version history view](#))



In SOC mode, you act as the admin of the respective company. An orange status bar below the top navigation bar indicates that you are in SOC mode for a company.

If you have opened a company and want to return to the overview of all companies in the **Company accounts** view, you must use the **Back to the overview** button. Using the back button in the browser does not work.

If you initiate manual mitigation for a company or make other changes in SOC mode, this will be recorded in the audit logs as a change made by you as a SOC user.

You are in SOC mode for: Muster GmbH

Back to the overview

1.3.2.1 Dashboard view



Figure 9: Dashboard view

The **Dashboard** view of the respective company provides you with access to various traffic diagrams that give you information about the company's networks.

The following diagrams are available in the **Dashboard** view:

Element	Description
Bandwidth per destination IP	This diagram shows the bandwidth per second for the available destination IPs.
Packets/s per destination IP	This diagram shows how many packets per second were sent to the respective destination IPs.
Packets/s per protocol	This diagram shows the number of packets received per second, grouped by transmission protocol. The legend below the diagram shows the names of the protocols recorded, for example, ICMP, TCP, UDP.
Packets/s per destination port	This diagram shows the number of packets received per second for the destination port. The numbers of the ports recorded can be found in the legend below the diagrams.
Packets/s per	

Element	Description
source port	This diagram shows the number of packets received per second for the source port. The numbers of the ports recorded can be found in the legend below the diagrams.
Legend filter	In addition to the filters above the diagrams, there are diagram-specific filters that can be set using the values in the legend. The following filters are available: IP : Bandwidth per destination IP and Packets/s per destination IP Protocol : Packets/s per protocol Port : Packets/s per destination port and Packets/s per source port



Figure 10: Filters in the dashboard

You can use filters to define the data shown:

Element	Description
Period	shows the data per second for the selected time intervals: 1 hour: shows the data per second for the selected hour. (default value) 2 hours: shows the data per second for the selected 2 hours. 3 hours: shows the data per second for the selected 3 hours. 4 hours: shows the data per second for the selected 4 hours. 6 hours: shows the data per second for the selected 6 hours. 12 hours: shows the data for the selected 12 hours aggregated in 10-second groups. 24 hours: shows the data for the selected 24 hours aggregated in 10-second groups. 7 days (only available for individual IP addresses): shows the data for the selected 7 days aggregated in groups of one hour.
Ending at	Defines the time period during which the data should be shown according to the time interval defined at Period. To change the date, select a date and time using the icon .

Element	Description
	★ If you select 1 hour as the period and 01.08.2024 12:00 as the end time, the data for the period from 01.08.2024 11:00 to 01.08.2024 12:00 is shown.
Units	For the Bandwidth per destination IP diagram, you can choose between the units Gbit/s , Mbit/s , Kbit/s , and bit/s . All other charts use the unit packets/s, which cannot be changed.
IP	Allows you to show data for specific IP addresses or entire networks using the following values: If a specific IP address is specified, the chart shows the data for that IP address. If a subnet mask (for example, /24) is entered, the chart shows the data for the entire network.

You can zoom in on any chart, which will enlarge the selected time period. To do this, select the desired area by holding down the left mouse button.

In addition, two buttons can be used to download the data for each diagram:

- **Download chart:** Downloads the chart as a PNG file.
- **Download report (.csv):** Downloads the data from the chart as a CSV file.

1.3.2.2 Networks view



To create and delete a network, as well as view and change settings, you need SOC administration rights.




Figure 11: Networks view

The **Networks** view provides an overview of the networks, the IP address ranges of the networks, the configured packet rate limit (in packets/s), the configured bandwidth limit (in MBit/s), and the mitigation status.

The following information is available:

Element	Description
Name	The name of the network.
IP Address	The IP address of the network.
Bandwidth limit (in MBit/s)	The maximum bandwidth allowed for your network.  If the network protection switch under Auto Actions is disabled, all values defined prior to deactivation are shown in grey.
Packet rate limit (in PPS)	The maximum number of packets per second allowed on the network.  If the network protection switch under Auto Actions is disabled, all values defined prior to deactivation are shown in grey.
Auto mitigation status	Shows the status of mitigation: Disabled : Automatic mitigation is disabled. Under mitigation : Mitigation has been initiated. Normal : Mitigation has been completed.
Manual mitigation status	Shows the status of manual mitigation: Under mitigation : A manual mitigation has been initiated. Normal : Manual mitigation has been completed.
START MANUAL MITIGATION	Open the Mitigate network or IP address(es) dialog to start mitigation for the selected network.

In addition, you have the following management and configuration options available:

Element	Description
	The icon enables you to search specifically for names, IP addresses, bandwidth, and packet rates.

Element	Description
	The icon allows you to sort individual columns.
Add Network	The button opens the Add new network dialog for adding a new network.
Resync Networks	The button synchronises all networks.
	The icon opens the Information about <network name> dialog for viewing all the settings defined for the selected network.
	The icon opens the Edit network dialog for editing the settings of the selected network.
	The icon opens the Delete network dialog for deleting the selected network.
	The mitigation icon next to the Networks view in the left navigation bar indicates whether at least one mitigation is running.

1.3.2.2.1 View network



To create and delete a network, as well as view and change settings, you need SOC administration rights.

Proceed as follows to view the settings for a network:



Figure 12: Icon for viewing the network

- Click on the  icon.
- ↳ The **Information about <network name>** dialog opens.




Figure 13: Information about network dialog

In the **Information about <network name>** dialog, you can view the following information:

Element	Description
Name	The name of the network.
IP Address	The IP address of the network.
Bandwidth Limit (in MBit/s)	The threshold value for the maximum possible bandwidth.
Packet Rate Limit (in PPS)	The threshold value for the maximum number of packets allowed per second.
Duration to Maintain Mitigation (in Sec)	The duration of mitigation in seconds after traffic has fallen below the thresholds.

Element	Description
Mitigation type	The way in which mitigation is carried out. The following values are available: CLOUD: If the threshold is exceeded, the traffic is filtered via the Myra data center.
Mitigation Strategy	Indicates whether only a single IP address or the entire network is automatically mitigated. The following values are available: IP: Only a single IP address of the network is automatically mitigated. CIDR: The entire network is automatically mitigated.
Notification email address	The email address of the users to whom mitigation notifications are sent.
Auto Actions	Indicates whether automatic mitigation is performed for the selected network or not. The following values are available: Network protection enabled: Automatic mitigation is enabled. Network protection disabled: Automatic mitigation is disabled.
Manual Mitigation	Shows whether a manual mitigation may be started for the network. ⓘ If the manual mitigation is disabled, the Mitigate button cannot be clicked.
Subnet mitigation override	Indicates whether the network supports the use of /32 or /28 subnets.



For a network in data-only mode, the dialog shows **Name** and **IP Address** only. All details about thresholds and mitigation are omitted, because no mitigation is performed for the network.

1.3.2.2.2 Add Network



To create and delete a network, as well as view and change settings, you need SOC administration rights.

Proceed as follows to add a new network to the list of networks for a company:



Figure 14: Button to add a network

- Click on the **Add Network** button.
- ↳ The **Add new network** dialog opens.



Add new network

NAME

BANDWIDTH LIMIT

DURATION TO MAINTAIN MITIGATION (IN SEC)

MITIGATION STRATEGY

Choose Strategy

AUTO ACTIONS

☒ Network protection enabled

☐ DATA ONLY

☐ Data only disabled

IP ADDRESS

PACKET RATE LIMIT

MITIGATION TYPE

Choose Mitigation type

NOTIFICATION EMAIL ADDRESS

MANUAL MITIGATION

☒ Manual mitigation enabled

☐ SUBNET MITIGATION OVERRIDE

☐ Subnet mitigation override disabled

Cancel

Save

Figure 15: Add network dialog

- Enter the name of the network in the field under **Name**.
- Enter the IP address of the network in the field under **IP Address**.

- ▶ Enter the maximum possible bandwidth in the field under **Bandwidth Limit (in MBit/s)**.



If the switch for the network protection under **Auto Actions** is disabled, no thresholds can be set.

- ▶ Enter the maximum number of permitted packets per second in the field under **Packet Rate Limit (in PPS)**.



If the switch for the network protection under **Auto Actions** is disabled, no thresholds can be set.

- ▶ In the field under **Duration to Maintain Mitigation (in Sec)**, enter the duration of the mitigation in seconds after the traffic has fallen below the thresholds.
- ▶ Select the corresponding mitigation variant from the drop-down list under **Mitigation type**. The following values are available:
 - **CLOUD**: If the threshold is exceeded, the traffic is filtered via the Myra data center.
- ▶ Select the corresponding value from the drop-down list under **Mitigation Strategy**. The following values are available:
 - **IP**: Only a single IP address of the network is automatically mitigated.
 - **CIDR**: The entire network is automatically mitigated.
- ▶ If necessary, enter an email address in the field under **Notification email address**.
- ▶ If necessary, disable the switch for the network protection under **Auto Actions**.



If automatic network protection is disabled, mitigation will not start automatically and must be performed manually.

The network is nevertheless visible in the list of networks in the **Networks** view.

- ▶ If necessary, enable the switch for the manual mitigation under **Manual Mitigation**.



If the manual mitigation is disabled, the **Mitigate** button cannot be clicked.

- If necessary, enable the switch under **Data only**.



In data-only mode, the traffic of the network is recorded only. The fields for the thresholds, the duration of the mitigation, the mitigation type, the mitigation strategy and the notification email address as well as the switches under **Auto Actions** and **Manual Mitigation** are hidden. No mitigation is performed for the network.


- If necessary, enable the switch under **Subnet mitigation override** to use IPv4 /28 and IPv6 /32 networks.
 - Click on the **Save** button.
- The new network is created and the traffic data appears in the **Dashboard** view.

1.3.2.2.3 Edit network



To create and delete a network, as well as view and change settings, you need SOC administration rights.

Proceed as follows to change a network:



NAME	IP ADDRESS	BANDWIDTH LIMIT (IN MBIT/S)	PACKET RATE LIMIT (IN PPS)	AUTO MITIGATION STATUS	MANUAL MITIGATION STATUS	START MANUAL MITIGATION	
Network 1	XXX.XXX.XXX.XXX/24	4000	500000	Normal	Under mitigation	Stop mitigation	ⓘ ⚙️ 🗑️
Network 2	XXX.XXX.XXX.XXX/24	4000	500000	Disabled	Normal	Mitigate	ⓘ ⚙️ 🗑️
Network 3	XXX.XXX.XXX.XXX/48	10000	800000	Normal	Normal	Mitigate	ⓘ ⚙️ 🗑️

ITEMS PER PAGE: 10 | 1-3 OF 3 ITEMS | 1 OF 1 PAGES

Figure 16: Icon for editing the network

- Click on the  icon.
- ↳ The **Edit network** dialog opens.



The 'Edit network' dialog box contains the following fields and controls:

- NAME:** Text input field with 'Network 1'.
- BANDWIDTH LIMIT:** Text input field with '4000'.
- DURATION TO MAINTAIN MITIGATION (IN SEC):** Text input field with '14400'.
- MITIGATION STRATEGY:** Dropdown menu with 'CIDR' selected.
- AUTO ACTIONS:**
 - ☒ Network protection enabled
 - ☐ Data only disabled
- IP ADDRESS:** Text input field with 'XXX.XXX.XXX.XXX/24'.
- PACKET RATE LIMIT:** Text input field with '500000'.
- MITIGATION TYPE:** Dropdown menu with 'CLOUD' selected.
- NOTIFICATION EMAIL ADDRESS:** Text input field with 'max.mustermann@example.com'.
- MANUAL MITIGATION:**
 - ☒ Manual mitigation enabled
- SUBNET MITIGATION OVERRIDE:**
 - ☐ Subnet mitigation override disabled

Buttons: Cancel, Save

Figure 17: Edit network dialog

- ▶ Adjust the data as needed.



If a mitigation is running, the manual mitigation cannot be disabled.

- ▶ Click on the **Save** button.
- A message confirms that the network settings have been successfully changed.

1.3.2.2.4 Delete network



To create and delete a network, as well as view and change settings, you need SOC administration rights.

Proceed as follows to delete a network:



Figure 18: Dialog for deleting the network

- ▶ Click on the  icon.
- ↳ The **Delete network** view opens.



Figure 19: Delete network dialog

- ▶ Click on the **Delete** button.
- A message confirms that the network has been successfully deleted, and the network disappears from the list of networks.

1.3.2.2.5 Start manual mitigations

-  Mitigations are only possible for the entire network.
-  You can only start a manual mitigation if the SOC admin has enabled it for the network.

If you suspect that a company has been targeted by an attack, you can initiate manual mitigation at any time.

Proceed as follows to start a manual mitigation:



Figure 20: Buttons for initiating mitigation

- Click on the **Mitigate** button.
- ↳ The **Mitigate network or IP address(es)** dialog opens.




Figure 21: Mitigate network or IP address(es) dialog

- Click on the **Mitigate** button.
- A message confirms that mitigation has started successfully.

Next to the **Networks** view in the left navigation bar, the mitigation icon  is visible, and in the **Manual mitigation status** column, the status changes to one of the following values:

- **Under mitigation:** Manual mitigation has been initiated for the entire network.



In the case of manual mitigation, traffic is redirected via the scrubbing center, attacks are mitigated or blocked, and you receive a notification via email.



The mitigation icon  next to the **Networks** view in the left navigation bar remains visible for as long as the Myra DataHub is running mitigations. The mitigation icon only disappears once all running mitigations have been stopped.

1.3.2.2.6 Stop manual mitigations

Proceed as follows to stop a manually started mitigation:



Figure 22: Buttons for ending a mitigation

- ▶ Click on the **Stop mitigation** button or the **(X) Stop mitigation(s)** button.
 - ↳ The **Mitigate network or IP address(es)** dialog opens.
- ▶ Click on the **Stop mitigation** button.




Figure 23: Dialog for finishing a mitigation - entire network



The mitigation icon  next to the **Networks** view in the left navigation bar remains visible for as long as the Myra DataHub is running mitigations. The mitigation icon only disappears once all running mitigations have been stopped.

1.3.2.3 Mitigation history view



NETWORK	STARTED	FINISHED	STARTED BY	ENDED BY	BANDWIDTH THRESHOLD (MBit/s)	PACKET RATE THRESHOLD (PACKETS/s)	TRIGGER TYPE	REPORT
XXXXXXX/24	02.05.2026 11:04	02.05.2026 11:52	Myra	Myra	4.000 / 3.884	500.000 / 486.210	Automatic	
XXXXXXX/24	07.05.2026 03:18	07.05.2026 04:06	Myra	Myra	4.000 / 3.912	500.000 / 491.075	Automatic	
XXXXXXX/24	14.05.2026 20:41	14.05.2026 21:12	max.mustermann@example.com	max.mustermann@example.com	4.000 / 4.000	500.000 / 500.000	Manual	
XXXXXXX/48	21.05.2026 08:55	21.05.2026 09:47	Myra	Myra	10.000 / 9.740	800.000 / 782.640	Automatic	
XXXXXXX/24	28.05.2026 16:22	28.05.2026 16:58	erika.musterrfrau@example.com	erika.musterrfrau@example.com	4.000 / 4.000	500.000 / 500.000	Manual	

Figure 24: Mitigation history view

In the **Mitigation history** view, you can see an overview of all mitigations that have been triggered automatically or manually. You can retrieve a mitigation report for each completed mitigation.

The following information is available:

Element	Description
Network	The IP address of the network.
Started	The date and time when mitigation was initiated.
Finished	The date and time at which the mitigation was completed.
Started by	Indicates who initiated the manual mitigation.
Ended by	Indicates who stopped the manual mitigation.
Bandwidth Threshold (MBit/s)	Shows the defined bandwidth threshold and threshold exceedance during automatic mitigation.
Packet Rate Threshold (Packets/s)	Shows the defined packet rate threshold and threshold exceedance during automatic mitigation.
Trigger type	Indicates whether mitigation was started manually or automatically.
Report	Enables the mitigation report to be opened in a new window via the icon  .

The following options are available:

Element	Description
	The icon enables you to search specifically for names, IP addresses, bandwidth, and packet rates.

1.3.2.3.1 Open mitigation reports

Proceed as follows to open the mitigation report:

- Click on the icon  in the **Report** column.
- The **Report - <Report Name> (<Company Name>)** view opens.

1.3.2.3.2 Mitigation reports view




Figure 25: Mitigation reports view

The **Report - <Report Name> (<Company Name>)** view provides an overview of the individual data collected during successful mitigation.

The following information is shown in the **Details** table:

Element	Description
Network	The IP address of the network.
Mitigation Timeframe	Shows the time period during which the mitigation was performed.

Element	Description
Bandwidth - Configured threshold	shows the configured bandwidth threshold at which automatic mitigation is triggered.
Bandwidth - Triggered by	shows the value that triggered automatic mitigation when the bandwidth threshold was exceeded.
Bandwidth - Peak	shows the peak value during mitigation.
Packets - Configured threshold	shows the configured packet rate threshold at which automatic mitigation is triggered.
Packets - Triggered by	shows the value that triggered automatic mitigation when the packet rate threshold was exceeded.
Packets - Peak	shows the peak value during mitigation.
Type	Indicates whether mitigation was started manually or automatically.

In addition, the mitigation report includes seven charts depicting the following periods:

- Network utilization during the first 24 hours before mitigation began
- Network utilization from the start to the end of mitigation

The following diagrams are available:

Element	Description
Bandwidth per destination IP	This diagram shows the bandwidth per second for the available destination IPs.
Packets/s per destination IP	This diagram shows how many packets per second were sent to the respective destination IPs.
	This diagram shows the number of packets received per second, grouped by transmission protocol. The legend below the diagram

Element	Description
Packets/s per protocol	shows the names of the protocols recorded, for example, ICMP, TCP, UDP.
Packets/s per destination port	This diagram shows the number of packets received per second for the destination port. The numbers of the ports recorded can be found in the legend below the diagrams.
Packets/s per source port	This diagram shows the number of packets received per second for the source port. The numbers of the ports recorded can be found in the legend below the diagrams.
Legend filter	In addition to the filters above the diagrams, there are diagram-specific filters that can be set using the values in the legend. The following filters are available: IP : Bandwidth per destination IP and Packets/s per destination IP Protocol : Packets/s per protocol Port : Packets/s per destination port and Packets/s per source port

You can download the reports as PDF files by clicking on the **Download report** button.

1.3.2.4 Anomaly history view



The **Anomaly history** view appears only if the anomaly feature is enabled for the company (see [Change company](#)).

Anomaly history						
STARTED	LAST UPDATED	TYPE	NETWORK	STATUS	ENDED	
22.05.2026 14:08	22.05.2026 14:26	Volumetric	XXX.XXX.XXX.XXX/24	Open		ⓘ
21.05.2026 08:55	21.05.2026 09:47	Amplification	XXXX.XXX.XXX.XXX/48	Closed	21.05.2026 09:47	ⓘ
19.05.2026 22:15	19.05.2026 22:41	Protocol	XXX.XXX.XXX.XXX/24	Update		ⓘ
14.05.2026 20:41	14.05.2026 21:12	Volumetric	XXX.XXX.XXX.XXX/24	Closed	14.05.2026 21:12	ⓘ
07.05.2026 03:18	07.05.2026 04:06	Amplification	XXX.XXX.XXX.XXX/24	Closed	07.05.2026 04:06	ⓘ
02.05.2026 11:04	02.05.2026 11:52	Volumetric	XXX.XXX.XXX.XXX/24	Closed	02.05.2026 11:52	ⓘ
ITEMS PER PAGE: 10 1-6 OF 6 ITEMS						
1 OF 1 PAGES						

Figure 26: Anomaly history view

In the **Anomaly history** view, you get an overview of all anomalies detected in the traffic of your networks. By default, the entries are sorted in descending order by the start of the anomaly.

The following information is available:

Element	Description
Started	The date and time at which the anomaly was detected.
Last updated	The date and time at which the entry was last updated.
Type	The type of the detected anomaly. The following values are available: Volumetric: A traffic flood aimed at saturating your bandwidth or packet capacity by sheer volume, regardless of the protocol used – for example extreme traffic bursts or floods from a large spread of source addresses. Protocol: An attack that abuses how a network protocol or connection setup works in order to exhaust connection tables, state, or processing resources rather than bandwidth – for example SYN floods or other anomalous TCP or UDP traffic. Amplification: An attack in which third-party servers on the internet are tricked into sending large responses to your address on behalf of a spoofed sender, so a small request turns into a much larger flood – for example DNS reflection.  The view can show several types at the same time for one anomaly.
Network	The network in CIDR notation in which the anomaly was detected.
Status	The current status of the anomaly. The following values are available: Open: Myra detected the anomaly and the anomaly continues. Update: New information about the anomaly is available. Closed: The anomaly has ended.
Ended	The date and time at which the anomaly ended.

The following options are available:

Element	Description
	The View details icon opens the Anomaly details dialog for the selected entry.
	The icon allows you to search by type, network, and status.
	If there are no anomalies, the view displays the text No anomalies found.

1.3.2.4.1 Anomaly details dialog




Figure 27: Anomaly details dialog

In the **Anomaly details** dialog, you can view the following information about an anomaly:

Element	Description
Network	The network in CIDR notation in which the anomaly was detected.

Element	Description
Type	The type of the detected anomaly.
Status	The current status of the anomaly.
Started	The date and time at which the anomaly was detected.
Last updated	The date and time at which the entry was last updated.
Ended	The date and time at which the anomaly ended.
Additional information	Further details about the anomaly provided by the detection.  If no further details are available, the area displays the text No additional information available.

1.3.2.5 Traffic Reports view



IP	CIDR	TOTAL TRAFFIC	TOTAL PACKETS
xxx.xxx.xxx.xxx	xxx.xxx.xxx.xxx/24	4.82 TB	6,184,902,115
xxx.xxx.xxx.xxx	xxx.xxx.xxx.xxx/24	1.24 TB	1,507,336,480
xxx.xxx.xxx.xxx	xxx.xxx.xxx.xxx/25	812.45 GB	946,128,703
xxx.xxx.xxx.xxx	xxx.xxx.xxx.xxx/26	317.90 GB	402,775,164
xxx.xxx.xxx.xxx	xxx.xxx.xxx.xxx/24	96.08 GB	128,440,592

Figure 28: Traffic Reports view

In the **Traffic Reports** view, you can view a summary of traffic for each IP address during the selected time period.

The following information is available:

Element	Description
IP	A specific IP address.
CIDR	The network to which the IP address is assigned.
TOTAL TRAFFIC	Shows all traffic that has passed through this IP address.
TOTAL PACKETS	Shows the total number of packets received via this IP address.

The following options are available:

Element	Description
Type of report	Using the drop-down menu for the report type, you can choose whether you want to see a breakdown by IP address for a specific day or for the current month.
Date	Select the day for which you want to view the traffic summary by IP address.  The drop-down list is only available if you have selected Daily as the report type.
	The symbol enables you to search specifically for the name of the report.
Download CSV	The button downloads the complete report as a CSV file.

1.3.2.6 Audit log view

	You need administrator rights to view the audit log.
---	--

Audit Log						
CREATED	PERFORMED BY	EVENT	RESOURCE	RESOURCE ID	PARAMETERS	
12.05.2026 09:14:22	max.mustermann@example.com	UPDATED	Network	XXXXXXX/24	bw_limit: 4000	
12.05.2026 09:02:47	max.mustermann@example.com	CREATED	Network	XXXXXXX/24	pps_limit: 500000	
11.05.2026 17:36:05	erika.musterfrau@example.com	UPDATED	User	erika.musterfrau@example.com	role: user	
11.05.2026 16:20:31	erika.musterfrau@example.com	CREATED	User	jan.belspiel@example.com	role: admin	
11.05.2026 14:58:12	jan.belspiel@example.com	DELETED	Network	XXXXXXX/48	—	
11.05.2026 11:41:09	jan.belspiel@example.com	UPDATED	Network	XXXXXXX/24	type: ACTION_BLACKHOLE	
10.05.2026 18:07:53	lena.sommer@example.com	CREATED	Network	XXXXXXX/24	bw_limit: 1000	
10.05.2026 15:22:40	tobias.winter@example.com	UPDATED	Network	XXXXXXX/24	duration: 14400	
10.05.2026 12:15:18	tobias.winter@example.com	DELETED	User	lena.sommer@example.com	—	
09.05.2026 08:49:02	max.mustermann@example.com	CREATED	Network	XXXXXXX/24	nettype: RIPE [P]	
ITEMS PER PAGE: 10 1-10 OF 37 ITEMS 1 OF 4 PAGES						

Figure 29: Audit log view

In the **Audit Log** view, you can find detailed information about all changes made for your own company.

The following information is available:

Element	Description
Created	The time and date when the change was made.
Performed by	The name of the user.
Event	The type of the activity. CREATED : A new entry has been created. UPDATED : An existing entry has been modified. DELETED : An existing entry has been deleted.
Resource	The place of change.
Resource ID	The entry that has been changed.
Parameters	The values of the corresponding entry that have been changed.

The following options are available:

Element	Description
	The symbol filters the reports by names.
Download CSV	The button downloads the complete monthly report as a CSV file.

1.3.3 Company management

The Myra DataHub provides two kinds of user management: a user management for creating SOC users and a user management per company for the customers.

Depending on who you want to create a new account for, proceed as follows:

Account for a SOC user:

- ▶ Open the Myra DataHub.
- ▶ Log in.
 - ↳ The Myra DataHub home page with the company accounts opens.



Figure 30: Opening user management – Option 1

- ▶ Click on the company name in the top right corner.
- The **Company management** view opens.

Account for a company

- ▶ Open the Myra DataHub.
- ▶ Log in.
 - ↳ The Myra DataHub home page with the company accounts opens.
- ▶ Click on the name of a company.
 - ↳ The **Dashboard** view of the respective company opens.



Figure 31: Opening user management – Option 1

- ▶ Click on the company name in the top right corner.
- The **Company management** view opens.


1.3.3.1 Company management view

In the **Company management** view, you can view, manage, and delete users. You can also customise the SIEM settings for the company and manage the recipients of the notifications.

The view contains the following tabs:

- User management
- SIEM Settings
- Notifications

1.3.3.2 User management tab



Company management

1 Add company member
Add a new member to your company.
Please provide the email address of the person you want to add.

EMAIL ADDRESS
jan.beispiel@example.com

What role do you want to assign to the new user?

☒ Administrator
Administrators can perform any action.

☐ User
Normal users have the ability to view data.

Save

2 List of User accounts

USER	ROLE	
Max Mustermann	Administrator	🗑️ 📄
Erika Musterfrau	User	🗑️ 📄
Jan Beispiel	User	🗑️ 📄
Lena Sommer	User	🗑️ 📄

ITEMS PER PAGE: 10 | 1-4 OF 4 ITEMS

1 OF 1 PAGES

Figure 32: Company management view

In the **User management** tab, you will find an overview of all the information and settings available to you for managing the users of a company.

The **User management** tab comprises two areas:

■ Add company member





Figure 33: Add company member area

Enables the creation of new users with admin and user rights. See [Section Add account](#).

The following information is available:

Element	Description
USER	The name of the user.  When adding a new user, the name before the @ symbol is stored in the system as the name of the user. The name can be changed later by the admin (see User Management view in the Myra App manual) or by the users themselves (see Edit user <email address> dialog in the Myra App manual).
ROLE	The permissions that users have within the company. The following values are available: Administrator: Users with the role Administrator may use every portal function. User: Users with the role User are restricted and may only view data.

■ List of User accounts



USER	ROLE		
Max Mustermann	Administrator		
Erika Musterfrau	User		
Jan Beispiel	User		
Lena Sommer	User		

Figure 34: List of user accounts area

shows all users created for the company.

The following options are also available:

Element	Description
	The icon opens the Remove company member dialog for deleting the selected user.
	The icon opens the Update company member dialog for changing the name and role of a user.
	The icon allows you to search specifically for user names.

1.3.3.2.1 Add account



Only accounts that have already been created in the Myra App can be added.

Proceed as follows to add a new account:

- Navigate to the **Add company member** area.




Figure 35: Add company member area

- ▶ Click on **Select user** in the drop-down list
- ▶ Select a user from the list or search for a specific user.
- ▶ Under **What role do you want to assign to the new user?**, select the corresponding permission group.

You have two permission groups to choose from:

- ↳ **Administrator:** Users with the role **Administrator** may use every portal function.
- ↳ **User:** Users with the role **User** are restricted and may only view data.
- ▶ Click on the **Save** button.
- A message confirms that the user has been successfully created. The new entry is also visible in the list of accounts.

1.3.3.2.2 Change account

Proceed as follows to change an account:


- ▶ Navigate to the **List of User accounts** area.



USER	ROLE
Max Mustermann	Administrator
Erika Musterfrau	User
Jan Beispiel	User
Lena Sommer	User
Tobias Winter	User

Figure 36: List of user accounts area

- ▶ Click on the icon  next to the relevant account.
- ↳ The **Update company member** dialog opens.



Update company member ✕

What role do you want to assign to the new user?

☐ Administrator
Administrators can perform any action.

☒ User
Normal users have the ability to view data.

Cancel Save

Figure 37: Update company member dialog

- ▶ If necessary, change the name of the user under **Name**.
- ▶ If necessary, change the user's authorization under Role.

You have two permission groups to choose from:

- ↳ **Administrator:** Users with the role **Administrator** may use every portal function.
- ↳ **User:** Users with the role **User** are restricted and may only view data.
- ▶ Click on the **Save** button.
- A message confirms that the account has been successfully changed.

1.3.3.3 SIEM Settings tab



To view the SIEM Settings tab, the option to use SIEM must be enabled in the organization settings.

In the **SIEM Settings** tab, you will find an overview of all the information and settings available to you for managing a company's users.

The following options are available:

Element	Description
	Defines the SIEM provider.

Element	Description
SIEM provider	 Currently, only Splunk is supported as an HTTP Event Collector (HEC).
Host	Defines the name of the host for data transfer.
Port	Defines the port of a host for the connection used to transfer data.
API tokens	 The API token used must be a HEX token.

The following information is shown in the SIEM log when SIEM is activated:

Data recorded in the SIEM log

Function	Event
Company	Edit company
Networks	Add Network
	Edit network
	Delete network
Mitigation	Automatic mitigation started
	Automatic mitigation completed
	Start Manual mitigation
	Stop manual mitigation
User management	Add account
	Delete account
	Verify email
	Reset password
	Enable and disable 2FA

The following information is not shown in the SIEM log:

Function	Event
Company	Edit company
SOC mode	Add SOC user/admin
	Delete SOC user/admin
	Verify email
	Reset password
	Enable and disable 2FA

1.3.3.4 Notifications tab




The **Notifications** tab is not displayed if you have opened the user management of your own SOC company as a SOC user.

In the **Notifications** tab, you can see which users of the company receive email notifications about anomalies and mitigations. You can also add additional recipients that are not users of the application.

The tab is divided into the following areas:

1.3.3.4.1 Notifications area



Notifications

Overview of all accounts and their alert notification preferences. Each user manages their own settings under Profile – Notifications.

☐ Show only users with email notifications enabled

USER	EMAIL ADDRESS	ROLE	EMAIL NOTIFICATIONS
Max Mustermann	max.mustermann@example.com	Administrator	✓ Enabled
Erika Musterfrau	erika.musterfrau@example.com	User	✓ Enabled
Jan Beispiel	jan.beispiel@example.com	User	✗ Disabled
Lena Sommer	lena.sommer@example.com	User	✓ Enabled
Tobias Winter	tobias.winter@example.com	User	✗ Disabled

Figure 38: Notifications area

The **Notifications** area contains an overview of all accounts and their alert notification preferences. Each user manages their own settings under **Profile** → **Notifications** (see [Notifications tab](#)).

The following information is available:

Element	Description
User	The name of the user.
Email address	The email address of the user.
Role	The role of the user in the company.
Email notifications	Indicates whether the user receives email notifications. The following values are available: Enabled: The user receives email notifications. Disabled: The user does not receive email notifications.


The following options are available:

Element	Description
Show only users with email notifications enabled	The checkbox hides all users without email notifications enabled.



If the checkbox is selected, a badge next to it shows the number of users with email notifications enabled. If no user matches the selected filter, the area displays the text **No users match the current filter.**

1.3.3.4.2 Additional contacts area



Additional contacts

Add people, systems, and shared mailboxes that are not users of the application to receive email notifications.

EMAIL ADDRESS: Add contact

EMAIL ADDRESS	STATE	ACTIONS
noc@example.com	Verified	
alerts@example.com	Verified	
soc@example.com	Pending	

Figure 39: Additional contacts area

In the **Additional contacts** area, you add people, systems, and shared mailboxes that are not users of the application to receive email notifications.

Proceed as follows to add an additional contact:

- ▶ Enter the email address of the contact in the field under **Email address**.
- ▶ Click on the **Add contact** button.
- The contact is added to the list and a verification email is sent. The contact remains in the **Pending** state until it is confirmed.

The following information is available:

Element	Description
Email address	The email address of the contact.
State	The state of the contact. The following values are available: Verified: The contact has confirmed the verification email and receives notifications. Pending: The contact has not confirmed the verification email yet.
Actions	The available actions for the contact.

The following options are available:

Element	Description
Resend verification email	The icon sends a new verification email to the contact.  The icon is only displayed for contacts in the Pending state.
Remove contact	The icon opens the Remove contact dialog for deleting the selected contact.



If no additional contacts have been added yet, the area displays the text **No additional contacts yet.**

1.3.4 Profile

Proceed as follows to view or change your profile information:

- ▶ Open the Myra DataHub.
- ▶ Log in.
 - ↳ The Myra DataHub home page with the company accounts opens.
- ▶ Click on the button with your profile picture in the top right corner.



Figure 40: Options under the profile picture

- ▶ In the menu, click on the **Profile** menu item.
- The **Profile** view opens.

The **Profile** view has the following tabs:

- Profile
- Notifications
- API tokens

1.3.4.1 Profile tab


In the **Profile** tab, you will find an overview of all the information and settings you can configure for your account.

The view is divided into four areas:

- **Profile information:** Information about view names and email addresses
- **Browser sessions:** Overview of all user sessions

1.3.4.1.1 Change username

In the **Profile information** area of the **Profile** view, you can change the name shown in the application.



The screenshot shows a 'Profile information' form with the subtitle 'Change your user account's profile information and email address.' It contains two input fields: 'NAME' with the value 'Max Mustermann' and 'EMAIL ADDRESS' with the value 'max.mustermann@example.com'. A 'Save' button is located at the bottom left of the form.


Figure 41: Personal account area

Proceed as follows to change the name:

- In the **Name** text field, replace the entered name with the new name.
- Click on the **Save** button.
- A message confirms that the name has been successfully changed.

1.3.4.1.2 Close active web browser sessions

In the **Browser sessions** area in the **Profile** view, you can log out of all web browser sessions other than the one currently running in the current browser window.



The screenshot shows a 'Browser sessions' table with the subtitle 'Manage and log out your active browser sessions on other browsers and devices.' The table has three columns: 'BROWSER', 'IP ADDRESS', and 'LAST ACTIVITY'. It contains two rows of data. At the top right, there is a search icon and a 'Log out other browser sessions' button. At the bottom left, there is a 'ITEMS PER PAGE' dropdown set to '10' and a '1-2 OF 2 ITEMS' indicator. At the bottom right, there is a '1 OF 1 PAGES' indicator and navigation arrows.

BROWSER	IP ADDRESS	LAST ACTIVITY
Firefox 138 - Windows	XXXXXX.XXX.XXX	This device
Chrome 137 - macOS	XXXXXX.XXX.XXX	12.05.2026 08:41

Figure 42: Active sessions area

Proceed as follows to log out of a web browser:

- Click on the **Log out other browser sessions** button.
- A message confirms the successful termination of inactive sessions.

 The current session in the current web browser will not be terminated.

1.3.4.2 Notifications tab



The **Notifications** tab appears if you are a member of a company. Myra only sends alerts about traffic anomalies if the anomaly feature is enabled for the respective company (see [Change company](#)).




Figure 43: Notifications tab

In the **Notifications** tab, you select how Myra notifies you about traffic anomalies and mitigations on your networks.

Myra sends an alert when Myra detects a traffic anomaly on your networks. Myra also sends an alert when a mitigation starts or stops.

The following types of mitigation trigger a notification:

- Automatic mitigations
- Manual mitigations
- Mitigations that the Myra support team starts

The following options are available:

Element	Description
Email notifications	The switch enables email alerts for anomalies and mitigation measures. The following values are available: Enabled: You receive email notifications. Disabled: You do not receive email notifications.

Proceed as follows to enable the email notifications:

- Enable the switch under **Email notifications**.
- The setting is saved immediately and the **Notifications updated** message appears.



As a SOC user, you are not automatically registered for the notifications of a company. Therefore, the tab does not show a switch, but only a corresponding note. To receive notifications, enter your email address as an additional contact in the respective company (see [Notifications tab](#)).

1.3.4.3 API tokens tab




Figure 44: API tokens tab

In the **API tokens** tab, you can create new API tokens, as well as view already added API tokens and delete them.

You need the API token for authentication via bearer tokens to use the API of the Myra DataHub. The token allows you to use Myra's APIv2 easily and securely by specifying the token as a bearer token in the header of your API request.

The tab is split into the following areas:

1.3.4.3.1 Create API token area

In the **Create API token** area, you can create new API tokens and set their validity period.

The following options are available:

Element	Description
Token name	The name of the token.
EXPIRES IN DAYS	The number of days the token is valid.
Save	The button creates the token and opens the API token created dialog for copying the token.

1.3.4.3.2 Manage API tokens area

An overview of all tokens.

The following information is available:

Element	Description
Name	The name of the token.
Created	The date and time when the token was generated.
Expires	The number of days the token is valid. <i>i</i> Specifying an expiration date is optional and does not need to be set when creating an API token. To increase security when using an API token, Myra recommends specifying an expiration date.
Last used	The date and time when the token was last used to execute an API request.

The following options are available:

Element	Description
	The icon opens the Delete API token dialog for deleting the selected entry.

Element	Description
Filter field	The field filters entries by names.

1.4 Permissions

1.4.1 Roles and permissions

Pages	Options	Company		SOC	
		User	Admin	User	Admin
Profile	Change name	Yes	Yes	Yes	Yes
	Change password	Yes	Yes	Yes	Yes
	Change two-factor authentication	Yes	Yes	Yes	Yes
	Close web browser session	Yes	Yes	Yes	Yes
Company	Show company page view	No	No	Yes	Yes
Company management	Edit company	No	No	No	Yes
Reports	Reports view	No	No	Yes	Yes
	Download reports	No	No	Yes	Yes
Audit log (SOC)	Audit Log view	No	No	Yes	Yes
	Download audit log	No	No	Yes	Yes
SOC mode	SOC mode	No	No	Yes	Yes
User management	Add account (company)	No	Yes (User & Admin)	Yes (User & Admin)	Yes (User & Admin)
	Change account (company)	No	Yes (User & Admin)	Yes (User & Admin)	Yes (User & Admin)

Pages	Options	Company		SOC	
		User	Admin	User	Admin
	Delete account (business)	No	Yes (User & Admin)	Yes (User & Admin)	Yes (User & Admin)
	Add account (SOC)	No	No	Yes (User)	Yes (User & Admin)
	Change account (SOC)	No	No	Yes (User)	Yes (User & Admin)
	Delete account (SOC)	No	No	Yes (User)	Yes (User & Admin)
Dashboard	Ansicht Dashboard	Yes	Yes	Yes	Yes
	Download diagrams	Yes	Yes	Yes	Yes
	Download reports	Yes	Yes	Yes	Yes
Networks	Networks view	Yes	Yes	Yes	Yes
	Start/stop manual mitigation	No	Yes	Yes	Yes
	Add Network	No	No	No	Yes
	Show network details	No	No	No	Yes
	Edit network	No	No	No	Yes
	Delete network	No	No	No	Yes
Mitigation history	Mitigation history view	Yes	Yes	Yes	Yes
	View mitigation report	Yes	Yes	Yes	Yes
		Yes	Yes	Yes	Yes

Pages	Options	Company		SOC	
		User	Admin	User	Admin
	Download mitigation report				
Audit log (company)	Audit Log view	No	Yes	Yes	Yes
	Download audit log	No	Yes	Yes	Yes
Manual	View user manual	Yes	Yes	Yes	Yes
Language	Change language	Yes	Yes	Yes	Yes
Change log	Version history of the Myra DataHub	No	No	Yes	Yes

2. API

2.1 Using the Myra API



Not all API endpoints are available to SOC users.

Whether an endpoint can be used with the API token of a SOC user is described in detail for each endpoint.

The Myra web API is based on REST and uses HTTP requests. Myra supports programmatic access to almost all operations that the user can perform via the web interface. For example, the user can create and configure new domains, manage the cache settings according to the deployment cycle, or change the DNS settings.

The Myra API for the Myra DataHub is available at: <https://networksecurity.myracloud.com/api/documentation>

Below, we explain the most important steps for registering with APIv2 and sending your first requests.

2.2 General

2.2.1 Getting access to the Myra API

You can authenticate with the Myra API using the following methods.

- Authentication using a bearer token by using an API token



When you send requests to the Myra DataHub through the API, the API token used has the same permissions as your account.

2.2.2 Authentication using bearer tokens

Proceed as follows to authenticate yourself on the API using a bearer token:

- ▶ Creating API token
- ▶ Enter bearer token in header

2.2.2.1 Creating API token

Proceed as follows to create an API token:

- ▶ Open the Myra DataHub.
- ▶ Log in.
- ▶ Open your personal account, see [Personal account](#).
 - ↳ The **Personal account** view opens.
- ▶ Click on the **API tokens** tab.



Figure 45: Enter the name and validity for the API token

- ▶ Navigate to the **Create API token** area.
- ▶ Enter a name in the text field under **TOKEN NAME**.



The name of an API token should help you to better identify the different purposes of your API tokens.

- ▶ If required, define a validity period for the API token in the text field under **EXPIRES IN DAYS**.



By default, an API token is valid for 90 days.

- ▶ Click on the **Save** button.
 - ↳ The **API token created** dialog opens.




Figure 46: Enter the name and validity for the API token

- To copy the API token data, click on the icon  next to each entry.



The API token can only be viewed while a new API token is being created and must be stored in a safe place.

As soon as you click on the Close button in the API token created dialog, you can only view the name, the creation date, and the expiry date.

If you have lost the token, you must generate a new API token.

- To close the dialog, click on the Close button.
- The new API token appears in the list of all API tokens and can be used immediately.

2.2.2.2 Request to the API using a bearer token

Proceed as follows to send a request to the API using a bearer token:

- Open the program you want to use to send the request.
- Add the method for the request.
- Add the API address together with the URI.



`https://networksecurity.myracloud.com/domains/1234`

- Add the token as a bearer token to the header as the authentication method.



`-H „Authorization: Bearer MY_API_TOKEN“`

- ▶ For PUT and POST requests, include a body in JSON format with the required information for the request.
- The request should look like this:

```
curl -X GET "https://networksecurity.myracloud.com/domains/1234"  
-H "Authorization: Bearer MY_API_TOKEN"
```

2.2.3 Used API methods

The Myra API for the Myra DataHub uses the following methods:

Element	Description
GET	The GET method allows you to request a specific object or a list of objects with settings and entries in the Myra DataHub.
POST	The POST method allows you to add new settings or entries for specific functions in the Myra DataHub.
PUT	The PUT method allows the user to change specific information of existing settings or entries in the Myra DataHub. Only the attributes <code>id</code>, <code>modified</code>, and the attributes for changing a specific option must be defined in the body.  The settings for subdomains are an exception, because changing a setting requires the complete transfer of all attributes of the corresponding object. Attributes that are not defined are reset to the default value.
DELETE	You can use the DELETE method to delete entire entries for an option in the Myra DataHub.

2.2.4 Possible responses to a request

All API requests return a status code and an object that provides information about the success or possible errors, such as missing information or permissions.

2.2.4.1 Possible status codes

Status code	Description	Object
200 OK	The request has succeeded.	QueryVO
201 Created	The request was successful and a new object was created.	ResultVO
202 Accepted	The request was successful but has not yet been completed. This may be the case if the request triggers a process, such as changing a configuration, which takes up to 7 minutes to be implemented.	ResultVO
400 Bad Request	The request was unsuccessful. The request was invalid or information is missing.	ViolationVO
401 Unauthorized	The request was unsuccessful because the request authentication was incorrect.	ViolationVO
403 Forbidden	The request was unsuccessful because the account used does not have the necessary permissions.	ViolationVO

2.2.4.2 Objects used

Element	Description
QueryVO	An object QueryVO is returned when a list of objects is received from a GET request.
ResultVO	For successful POST, PUT, and DELETE requests, an object ResultVO is returned.

In the case of invalid requests, an object **ViolationVO** is returned.

Element	Description
Violation	
VO	

2.3 API endpoints

In the following sections, we list all endpoints for our API that you can use to configure the Myra DataHub.

Alternatively, you can find all endpoints in our Swagger documentation at:

- <https://networksecurity.myracloud.com/api/documentation>

2.3.1 Organisation management

2.3.1.1 Deleting an organisation



Deleted organisations cannot be restored. After deletion, the organisation must be created again in order to continue using it.



This request is available to SOC users only.



An organisation cannot be deleted while an active mitigation is running for one of its networks.

Sends a `DELETE` request to the endpoint `/organisations/{organisation}`.

2.3.1.1.1 Description

The Delete-Organisation request deletes an organisation from the system.

2.3.1.1.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.1.3 Request

To delete an organisation, add the **Organisation ID** {organisation} to the path of the request.

No further information is required.

In response to a successful request, the system returns only the HTTP status code 200.

2.3.1.1.4 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
400	The request was unsuccessful. The request was invalid or information is missing.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.1.2 Deleting the SIEM configuration of an organisation



Deleted entries cannot be restored. To use an entry again after deletion, create it anew.

Sends a `DELETE` request to the endpoint `/organisations/{organisation}/siem`.

2.3.1.2.1 Description

The Delete-Organisation-SIEM request deletes the SIEM configuration of the organisation.

2.3.1.2.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.2.3 Request

To delete the SIEM configuration, add the **Organisation ID** {organisation} to the path of the request.

No further information is required.

In response to a successful request, the system returns only the HTTP status code 200.

2.3.1.2.4 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.1.3 Listing organisations with network and mitigation details



The `OrganisationV0` objects are wrapped in `data`, supplemented by the pagination blocks `links` and `meta`.

Sends a `GET` request to the endpoint `/organisations`.

2.3.1.3.1 Description

The List-Organisations-Paginated request returns a paginated list of all organisations, enriched with network CIDRs and the current mitigation status.

2.3.1.3.2 Requirements

Values of the request: none

Objects: none

2.3.1.3.3 Request

To request a paginated list of all organisations, no additional information is required in the path of the request.

As a result, the user gets one or more objects `OrganisationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the organisation.	string
name	The name of the organisation.	string
created_at	The original creation timestamp in ISO 8601 format.	string(\$date-time)
updated_at	The last update timestamp in ISO 8601 format.	string(\$date-time)
users	The users assigned to the organisation.	array
showReports	Defines whether mitigation reports are enabled.	true false
siemEnabled	Defines whether the SIEM integration is enabled.	true false
cidrs	The comma-separated list of CIDRs.	string
under_mitigation	Shows whether a network is currently in mitigation.	true false

2.3.1.3.4 Example

Example response:

```
{
  "data": [
    {
      "id": "xY9pQ5wR1",
      "name": "Test Organisation",
      "created_at": "2026-01-01T00:00:00+00:00",
      "updated_at": "2026-01-01T00:00:00+00:00",
      "users": [
        {
          "id": "xY9pQ5wR1",
          "name": "Max Mustermann",
          "email": "max@mustermann.de",
          "has2Fa": false,
          "permissions": {},
          "activeOrganisation": {
            "id": "xY9pQ5wR1",
            "name": "Test Organisation"
          }
        }
      ]
    }
  ]
}
```

```

    },
    "hasActiveMitigations": false,
    "hasSiem": false,
    "invitedSince": "2024-01-15 10:30:00",
    "status": "active",
    "role": "admin",
    "teams": [
      {
        "id": "xY9pQ5wR1",
        "name": "Test Organisation"
      }
    ],
    "teams_as_admin": [
      {
        "id": "xY9pQ5wR1",
        "name": "Test Organisation"
      }
    ],
    "features": [
      {
        "name": "L_NUMBER",
        "value": null,
        "enabled": 1
      }
    ]
  },
  "showReports": true,
  "siemEnabled": false,
  "cidrs": "127.0.0.1/32, 10.0.0.0/24",
  "under_mitigation": false
},
"links": {
  "first": "https://datahub-api.com/api/networks?page=1",
  "last": "https://datahub-api.com/api/networks?page=5",
  "prev": null,
  "next": "https://datahub-api.com/api/networks?page=2"
},
"meta": {
  "current_page": 1,
  "from": 1,
  "last_page": 5,
  "links": [
    {
      "url": "https://datahub-api.com/api/networks?page=2",
      "label": "Next »",
      "active": false
    }
  ]
},
"path": "https://datahub-api.com/api/networks",
"per_page": 15,
"to": 15,
"total": 64

```



2.3.1.3.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.1.4 Listing all organisations of the user

Sends a GET request to the endpoint `/organisations/all`.

2.3.1.4.1 Description

The List-Organisations request returns a list of all organisations to which the user has access.

2.3.1.4.2 Requirements

Values of the request: none

Objects: none

2.3.1.4.3 Request

To request a list of all organisations, no additional information is required in the path of the request.

As a result, the user gets one or more objects `OrganisationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the organisation.	string
name	The name of the organisation.	string
created_at	The creation date in ISO 8601 format.	string(\$date-time)
updated_at	The last modification date in ISO 8601 format.	string(\$date-time)

The response is not paginated.

2.3.1.4.4 Example

Example response:

```
[
  {
    "id": "xY9pQ5wR1",
    "name": "Test Organisation",
    "created_at": "2026-01-01T00:00:00+00:00",
    "updated_at": "2026-01-01T00:00:00+00:00",
    "users": [
      {
        "id": "xY9pQ5wR1",
        "name": "Max Mustermann",
        "email": "max@mustermann.de",
        "has2Fa": false,
        "permissions": {},
        "activeOrganisation": {
          "id": "xY9pQ5wR1",
          "name": "Test Organisation"
        },
        "hasActiveMitigations": false,
        "hasSiem": false,
        "invitedSince": "2024-01-15 10:30:00",
        "status": "active",
        "role": "admin",
        "teams": [
          {
            "id": "xY9pQ5wR1",
            "name": "Test Organisation"
          }
        ],
        "teams_as_admin": [
          {
            "id": "xY9pQ5wR1",
```

```

        "name": "Test Organisation"
      }
    ],
    "features": [
      {
        "name": "L_NUMBER",
        "value": null,
        "enabled": 1
      }
    ]
  }
],
"showReports": true,
"siemEnabled": false,
"customer_id": "abc",
"cidrs": "127.0.0.1/32, 10.0.0.0/24",
"under_mitigation": false,
"customer_reference": "abc"
}
]

```

2.3.1.4.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.

2.3.1.5 Getting an organisation by ID

Sends a GET request to the endpoint `/organisations/{organisation}`.

2.3.1.5.1 Description

The Get-Organisation request returns a single organisation for a specified ID.

2.3.1.5.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.5.3 Request

To request an organisation, add the **Organisation ID** {organisation} to the path of the request.

As a result, the user gets an object `OrganisationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the organisation.	string
name	The name of the organisation.	string
created_at	The original creation time in ISO 8601 format.	string(\$date-time)
updated_at	The time of the last update in ISO 8601 format.	string(\$date-time)
users	The users belonging to the organisation.	array
showReports	Defines whether mitigation reports are enabled.	true false
siemEnabled	Defines whether the SIEM integration is enabled.	true false

2.3.1.5.4 Example

Example response:

```
{
  "id": "xY9pQ5wR1",
  "name": "Test Organisation",
  "created_at": "2026-01-01T00:00:00+00:00",
  "updated_at": "2026-01-01T00:00:00+00:00",
  "users": [
    {
      "id": "xY9pQ5wR1",
      "name": "Max Mustermann",
      "email": "max@mustermann.de",
      "has2Fa": false,
      "permissions": {},
      "activeOrganisation": {
        "id": "xY9pQ5wR1",
        "name": "Test Organisation"
      }
    }
  ]
}
```

```
    },
    "hasActiveMitigations": false,
    "hasSiem": false,
    "invitedSince": "2024-01-15 10:30:00",
    "status": "active",
    "role": "admin",
    "teams": [
      {
        "id": "xY9pQ5wR1",
        "name": "Test Organisation"
      }
    ],
    "teams_as_admin": [
      {
        "id": "xY9pQ5wR1",
        "name": "Test Organisation"
      }
    ],
    "features": [
      {
        "name": "L_NUMBER",
        "value": null,
        "enabled": 1
      }
    ]
  },
  "showReports": true,
  "siemEnabled": false,
  "cidrs": "127.0.0.1/32, 10.0.0.0/24",
  "under_mitigation": false
}
```

2.3.1.5.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.1.6 Listing all mitigations of an organisation



The threshold and traffic metrics – `configured_bw`, `configured_pps`, `configured_bw_percentage`, `configured_pps_percentage`, `actual_bw`, `actual_pps`, `peak_bw`, `peak_pps`, `total_bw`, `total_pps` and (if the dropped data report function is enabled) `dropped_bits` and `dropped_packets` – are only returned for automatic mitigations triggered by detection. They are omitted for manual mitigations, which contain no detection data.

Sends a GET request to the endpoint `/organisations/{organisation}/mitigations`.

2.3.1.6.1 Description

The List-Organisation-Mitigations request returns a list of all mitigations for a specified organisation.

2.3.1.6.2 Requirements

Values of the request: **Organisation ID** `{organisation}`

Objects: none

2.3.1.6.3 Request

To request a list of all mitigations, add the **Organisation ID** `{organisation}` to the path of the request.

As a result, the user gets one or more objects `MitigationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The ID of the mitigation.	string
<code>organisation</code>	The associated organisation, specified as an object.	object
<code>network</code>	The mitigated network or, in the case of a partial mitigation, the specific IP address.	string

Attributes	Description	Values
mitigation_ type	The type of the applied mitigation.	ACTION_BL ACKHOLE ACTION_MI TIGATE_ON PREM ACTION_MI TIGATE_CL LOUD
mitigation_ cause	How the mitigation was triggered.	MANUAL_TR IGGER AUTO_TRIG GER OPS_TRIGG ER UNKNOWN_T RIGGER
start	The start date of the mitigation in ISO 8601 format.	string(\$date-time)
end	The end date of the mitigation in ISO 8601 format.	string(\$date-time)
created_at	The creation date in ISO 8601 format.	string(\$date-time)
updated_at	The last modification date in ISO 8601 format.	string(\$date-time)
actual_bw	The actual bandwidth of the mitigation.	number(\$float)
actual_pps	The actual packets per second of the mitigation.	number(\$float)
configured_ bw	The configured bandwidth of the mitigation.	number(\$float)
configured_ pps	The configured packets per second of the mitigation.	number(\$float)

Attributes	Description	Values
configured_bw_percentage	The configured bandwidth as a percentage.	number
configured_pps_percentage	The configured packets per second as a percentage.	number
peak_bw	The peak bandwidth of the mitigation.	number(float)
peak_pps	The peak packets per second of the mitigation.	number(float)
total_bw	The total bandwidth of the mitigation.	number(float)
total_pps	The total packets per second of the mitigation.	number(float)
has_report	Shows whether a report is available for the mitigation.	true false
start_user	The users who started the mitigation, specified as an object with ID and display name.	object
end_user	The users who ended the mitigation, specified as an object with ID and display name. The value is null while the mitigation is still running.	object

2.3.1.6.4 Example

Example response:

```
{
  "data": [
    {
      "id": "xY9pQ5wR1",
      "organisation": {
        "id": "aB3cD4eF5",
        "name": "ACME GmbH"
      },
      "network": "192.0.2.0/24",
      "mitigation_type": "ACTION_MITIGATE_ONPREM",
    }
  ]
}
```

```

    "mitigation_cause": "MANUAL_TRIGGER",
    "start": "2026-01-01T00:00:00+00:00",
    "end": "2026-01-01T00:00:00+00:00",
    "created_at": "2026-01-01T00:00:00+00:00",
    "updated_at": "2026-01-01T00:00:00+00:00",
    "actual_bw": 0,
    "actual_pps": 0,
    "configured_bw": 0,
    "configured_pps": 0,
    "configured_bw_percentage": 0,
    "configured_pps_percentage": 0,
    "peak_bw": 0,
    "peak_pps": 0,
    "total_bw": 0,
    "total_pps": 0,
    "has_report": true,
    "start_user": {
      "id": "pQ7rS8tU9",
      "name": "Max Mustermann"
    },
    "end_user": {
      "id": "pQ7rS8tU9",
      "name": "Max Mustermann"
    }
  },
  "links": {
    "first": "https://datahub-api.com/api/networks?page=1",
    "last": "https://datahub-api.com/api/networks?page=5",
    "prev": null,
    "next": "https://datahub-api.com/api/networks?page=2"
  },
  "meta": {
    "current_page": 1,
    "from": 1,
    "last_page": 5,
    "links": [
      {
        "url": "https://datahub-api.com/api/networks?page=2",
        "label": "Next »",
        "active": false
      }
    ]
  },
  "path": "https://datahub-api.com/api/networks",
  "per_page": 15,
  "to": 15,
  "total": 64
}

```

2.3.1.6.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.1.7 Listing all networks of an organisation



The `pps_limit_percentage` and `bw_limit_percentage` attributes are only present if percentage thresholds are enabled for the organisation.

Sends a GET request to the endpoint `/organisations/{organisation}/networks`.

2.3.1.7.1 Description

The List-Organisation-Networks request returns a paginated list of all networks of a specified organisation.

2.3.1.7.2 Requirements

Values of the request: **Organisation ID** `{organisation}`

Objects: none

2.3.1.7.3 Request

To request a list of all networks of an organisation, add the **Organisation ID** `{organisation}` to the path of the request.

As a result, the user gets one or more objects `NetworkV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the network.	string
organisation	The associated organisation, referenced by ID and name.	object
name	The name of the network.	string
cidr	The CIDR range of the network.	string
enabled	Shows whether automatic mitigation is enabled.	true false
data_only	Shows whether the network is monitored only, that is, it is visible in the dashboard but cannot be mitigated.	true false
mitigation_type	The mitigation type of the network.	ACTION_BLACKHOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
auto_mitigation_strategy	The automatic mitigation strategy of the network.	string
duration	The duration of the automatic mitigation.	integer
subnet_mitigation_override	The mitigation override for the subnet.	true false
pps_limit	The configured limit for packets per second.	integer
bw_limit	The configured bandwidth limit.	integer
autoStatus	Shows whether the network is currently under automatic mitigation.	true false
manualStatus	Shows whether the network is currently under manual mitigation.	true false

Attributes	Description	Values
active_partial_manual_mitigations	The active partial manual mitigations.	array
active_partial_auto_mitigations	The active partial automatic mitigations.	array
allow_manual_mitigation	Shows whether manual mitigations may be started for the network.	true false
extra	Additional custom fields defined for the organisation.	object

2.3.1.7.4 Example

Example response:

```
{
  "data": [
    {
      "id": "xY9pQ5wR1",
      "organisation": {
        "id": "aB3cD4eF5",
        "name": "ACME GmbH"
      },
      "name": "Customer-A-Prod",
      "cidr": "192.0.2.0/24",
      "enabled": true,
      "data_only": false,
      "mitigation_type": "ACTION_BLACKHOLE",
      "auto_mitigation_strategy": "IP",
      "duration": 0,
      "subnet_mitigation_override": false,
      "pps_limit": 0,
      "bw_limit": 0,
      "autoStatus": true,
      "manualStatus": true,
      "active_partial_manual_mitigations": [
        {}
      ],
      "active_partial_auto_mitigations": [
        {}
      ],
      "allow_manual_mitigation": true,
      "extra": {}
    }
  ]
}
```

```

    ],
    "links": {
      "first": "https://datahub-api.com/api/networks?page=1",
      "last": "https://datahub-api.com/api/networks?page=5",
      "prev": null,
      "next": "https://datahub-api.com/api/networks?page=2"
    },
    "meta": {
      "current_page": 1,
      "from": 1,
      "last_page": 5,
      "links": [
        {
          "url": "https://datahub-api.com/api/networks?page=2",
          "label": "Next »",
          "active": false
        }
      ]
    },
    "path": "https://datahub-api.com/api/networks",
    "per_page": 15,
    "to": 15,
    "total": 64
  }
}

```

2.3.1.7.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.1.8 Listing all users of an organisation

Sends a GET request to the endpoint `/organisations/{organisation}/users`.

2.3.1.8.1 Description

The List-Organisation-Users request returns a list of all users of a specified organisation, with the exception of agent accounts.

2.3.1.8.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.8.3 Request

To request a list of all users of an organisation, add the **Organisation ID** {organisation} to the path of the request.

As a result, the user gets one or more objects `UserV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the user.	string
name	The full name of the user.	string
email	The email address of the user.	string
role	The role of the user within the organisation.	admin editor
status	The current status of the user account.	string
invitedSince	The date on which the user was invited, or empty if the invitation has already been accepted.	string(\$date-time)
has2Fa	Defines whether two-factor authentication is enabled for the user.	true false

2.3.1.8.4 Example

Example response:

```
[
  {
    "id": "xY9pQ5wR1",
    "name": "Max Mustermann",
    "email": "max@mustermann.de",
    "has2Fa": false,
    "permissions": {},
    "activeOrganisation": {
      "id": "xY9pQ5wR1",
      "name": "Test Organisation"
    },
    "hasActiveMitigations": false,
    "hasSiem": false,
    "invitedSince": "2024-01-15 10:30:00",
    "status": "active",
    "role": "admin",
    "teams": [
      {
        "id": "xY9pQ5wR1",
        "name": "Test Organisation"
      }
    ],
    "teams_as_admin": [
      {
        "id": "xY9pQ5wR1",
        "name": "Test Organisation"
      }
    ],
    "features": [
      {
        "name": "L_NUMBER",
        "value": null,
        "enabled": 1
      }
    ]
  }
]
```

2.3.1.8.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.1.9 Changing the settings of an organisation

Sends a PATCH request to the endpoint `/organisations/{organisation}`.

2.3.1.9.1 Description

SOC only. The Change-Organisation request changes the settings of an organisation.

2.3.1.9.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.9.3 Request

To change the settings of an organisation, add the **Organisation ID** {organisation} to the path of the request.

For a detailed specification of which information is required to change the settings of an organisation, the following attributes can be defined in the body.

The following attributes are optional:

Attributes	Description	Values
name	The name of the organisation.	string
showReports		true

Attributes	Description	Values
	Defines whether reports are shown for this organisation.	false
siemEnabled	Defines whether SIEM is enabled for this organisation.	true false
siemProvider	The name of the SIEM provider.	string
trafficReportsEnabled	Shows whether traffic reports can be shown and downloaded for this organisation.	true false

In response to a successful request, the system returns only an HTTP status code 200.

2.3.1.9.4 Example

Example request body:

```
{
  "name": "string",
  "showReports": true,
  "siemEnabled": true,
  "siemProvider": "string",
  "trafficReportsEnabled": true
}
```

2.3.1.9.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	

STATUS CODE	DESCRIPTION
	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.1.10 Changing the SIEM configuration of an organisation



The body must contain the `id` and `modified` attributes in order to identify the corresponding entry.



The ID of the entry in the request path must match the value of the `id` attribute in the body.

Sends a `PATCH` request to the endpoint `/organisations/{organisation}/siem`.

2.3.1.10.1 Description

The Change-Organisation-SIEM request changes the SIEM connection details of an organisation.

2.3.1.10.2 Requirements

Values of the request: **Organisation ID** `{organisation}`

Objects: `OrganisationV0`

2.3.1.10.3 Request

To change the SIEM connection details, add the **Organisation ID** `{organisation}` to the path of the request.

For a detailed specification of which information is required to change the SIEM connection details, an object `OrganisationV0` with the following attributes must be defined in the body:

Attributes	Description	Values
<code>id</code>	The ID of the entry.	integer
<code>modified</code>	The last modification date in ISO 8601 format.	<code>string(\$date-time)</code>

The following attributes are optional:

Attributes	Description	Values
<code>siemProvider</code>	The name of the SIEM provider (for example splunk).	string
<code>siemConnectionDetails</code>	The connection details for the SIEM provider.	objects

In response, the system returns the object `OrganisationV0` with the updated information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The ID of the organisation.	string
<code>name</code>	The name of the organisation.	string
<code>created_at</code>	The original creation time.	<code>string(\$date-time)</code>
<code>updated_at</code>	The time of the last update.	<code>string(\$date-time)</code>
<code>users</code>	The users assigned to the organisation.	array
<code>showReports</code>	Defines whether mitigation reports are enabled.	true false
<code>siemEnabled</code>	Defines whether the SIEM integration is enabled.	true false

2.3.1.10.4 Example

Example request body:

```
{
  "siemProvider": "string",
  "siemConnectionDetails": {
    "host": "string",
    "port": 0,
    "apiToken": "string"
  }
}
```

2.3.1.10.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.1.11 Changing users within an organisation



The body must contain the `id` and `modified` attributes in order to identify the corresponding entry.



The ID of the entry in the request path must match the value of the `id` attribute in the body.

Sends a PATCH request to the endpoint `/organisations/{organisation}/users/{user}`.

2.3.1.11.1 Description

The Update-Organisation-User request changes the name and role of a user within a specific organisation.

2.3.1.11.2 Requirements

Values of the request: **Organisation ID** {organisation} ; **User ID** {user}

Objects: none

2.3.1.11.3 Request

To change a user within an organisation, add the **Organisation ID** {organisation} and the **User ID** {user} to the path of the request.

For a detailed specification of which information is required to change a user, the following attributes must be defined in the body:

Attributes	Description	Values
id	The ID of the user.	string
modified	The last modification date in ISO 8601 format.	string(\$date-time)

The following attributes are optional:

Attributes	Description	Values
name	The new name of the user.	string
role	The new role of the user.	admin editor

As a result, the user gets an object with the requested information.

The object provides the following information:

Attribute s	Description	Values
id	The ID of the user.	string
name	The name of the user.	string
email	The email address of the user.	string
status	The current status of the user.	string
invitedSi nce	The date on which the user was invited, or empty if the invitation has already been accepted.	string
role	The role of the user within the organisation.	admin editor

2.3.1.11.4 Example

Example request body:

```
{
  "name": "string",
  "role": "string"
}
```

2.3.1.11.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	

STATUS CODE	DESCRIPTION
	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.1.12 Adding an organisation



The body does not contain the `id`, `created`, and `modified` attributes. The system sets these values after the entry has been created.



This request is available to SOC users only.

Sends a POST request to the endpoint `/organisations`.

2.3.1.12.1 Description

The Add-Organisation request adds a new organisation to the system.

2.3.1.12.2 Requirements

Values of the request: none

Objects: OrganisationV0

2.3.1.12.3 Request

To add an organisation, no additional information is required in the path of the request.

For a detailed specification of which information is required to add an organisation, an object `OrganisationV0` with the following attributes must be defined in the body:

Attribute	Description	Values
<code>name</code>	The name of the organisation. Maximum length: 255 characters.	string

The following attributes are optional:

Attributes	Description	Values
showReports	Defines whether mitigation reports are enabled.	true false
siemEnabled	Defines whether the SIEM integration is enabled.	true false

In response, the system returns the object `OrganisationV0` with the information about the new entry.

2.3.12.4 Example

Example request body:

```
{
  "name": "string",
  "showReports": true,
  "siemEnabled": true
}
```

2.3.12.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.1.13 Resending the confirmation email for a notification address



The address must already be registered for the organisation and must not yet be verified; otherwise the request returns a 404 or 409 error.



For this request, you need administration rights for the organisation or SOC rights.



A maximum of five requests per hour to this endpoint is possible.

Sends a POST request to the endpoint `/organisations/{organisation}/notification-emails/resend`.

2.3.1.13.1 Description

The Resend-Verification request resends the confirmation email for an unverified notification address of an organisation.

2.3.1.13.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.13.3 Request

To resend the confirmation email, add the **Organisation ID** {organisation} to the path of the request and define the target address in the body:

Attribute	Description	Values
email	The notification address to which the confirmation email is resent.	string

In response to a successful request, the system returns only the HTTP status code 200.

2.3.13.4 Example

Example request body:

```
{
  "email": "alerts@example.com"
}
```

2.3.13.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
404	The request was unsuccessful because the requested resource was not found.
409	The request was unsuccessful because there is a conflict with the current state.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.14 Adding users to the organisation



The `userId` and `userFullName` attributes are required for Myra deployments.

Sends a POST request to the endpoint `/organisations/{organisation}/users/add`.

2.3.1.14.1 Description

The Add-Organisation-User request adds users to a specified organisation.

2.3.1.14.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: UserV0

2.3.1.14.3 Request

To add users to the organisation, add the **Organisation ID** {organisation} to the path of the request.

For a detailed specification of which information is required to add users, an object UserV0 with the following attributes must be defined in the body:

Attributes	Description	Values
userEmail	The email address of the user.	string
userRole	The role of the users.	admin editor

The following attributes are optional:

Attributes	Description	Values
userId (required for Myra deployments)	The MyraCloud ID of the users.	integer
userFullName (required for Myra deployments)	The full name of the user.	string

As a result, the system returns the object `message`, confirming that the users have been added.

The object provides the following information:

Attributes	Description	Values
message	The confirmation message of the request.	string

2.3.1.14.4 Example

Example request body:

```
{
  "userEmail": "string",
  "userRole": "string",
  "userId": 0,
  "userFullName": "string"
}
```

2.3.1.14.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.1.15 Removing a user from an organisation



Users cannot remove their own account from an organisation, regardless of their role; such an attempt returns the response 403 .

Sends a POST request to the endpoint `/organisations/{organisation}/users/remove` .

2.3.1.15.1 Description

The Remove-Organisation-User request removes a user from a specified organisation.

2.3.1.15.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.15.3 Request

To remove a user from an organisation, add the **Organisation ID** {organisation} to the path of the request.

For a detailed specification of which information is required to remove a user from the organisation, the following attribute must be defined in the body:

Attributes	Description	Values
userId	The ID of the user to be removed.	string

As a result, the user gets an object with a confirmation message.

The object provides the following information:

Attributes	Description	Values
message	The confirmation message returned after the user is removed.	string

2.3.1.15.4 Example

Example request body:

```
{
  "userId": "string"
}
```

2.3.1.15.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
404	The request was unsuccessful because the requested resource was not found.

2.3.1.16 Adding a notification address to the organisation



For this request, you need administration rights for the organisation or SOC rights.



The address must not already be registered for the organisation; otherwise the request returns a 422 error.

Sends a POST request to the endpoint `/organisations/{organisation}/notification-emails`.

2.3.1.16.1 Description

The Add-Notification-Email request allows you to register an additional notification contact for an organisation that is not a user of the application, for example a shared mailbox or an external partner. A verification email is sent to the address so the contact can confirm the enrolment.

2.3.1.16.2 Requirements

Values of the request: **Organisation ID** {organisation}

Objects: none

2.3.1.16.3 Request

To add a notification contact, add the **Organisation ID** {organisation} to the path of the request and define the target address in the body:

Attributes	Description	Values
email	The notification address to add.	string

As a result, you get the created object `NotificationEmail`. The contact remains unverified until the recipient confirms the verification email.

The object provides the following information:

Attributes	Description	Values
id	The ID of the notification address.	string
email	The notification address.	string
verified	Indicates whether the address has been verified.	true , false
verified_at	The date and time when the address was verified in ISO 8601 format. While the address is unverified, the value is null .	string(\$date-time)

2.3.1.16.4 Example

Example request body:

```
{
  "email": "alerts@example.com"
}
```

2.3.1.16.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
201	The request has succeeded and the notification address has been created.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.1.17 Deleting a notification address from the organisation



For this request, you need administration rights for the organisation or SOC rights.

Sends a DELETE request to the endpoint `/organisations/{organisation}/notification-emails/{notificationEmail}`.

2.3.1.17.1 Description

The Remove-Notification-Email request allows you to remove an additional notification contact from an organisation.

2.3.1.17.2 Requirements

Values of the request: **Organisation ID** {organisation} , **Notification address ID** {notificationEmail}

Objects: none

2.3.17.3 Request

To remove a notification contact, add the **Organisation ID** {organisation} and the **Notification address ID** {notificationEmail} to the path of the request.

In response to a successful request, the system returns only the HTTP status code 204.

2.3.17.4 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
204	The request has succeeded and the response has no content.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
404	The request was unsuccessful because the requested resource was not found.

2.3.2 Networks

2.3.2.1 Deleting a network from the organisation



Deleted networks cannot be restored. To continue using a network after deletion, create it anew.



This request is available to SOC users only.

Sends a `DELETE` request to the endpoint `/networks/{network}` .

2.3.2.1.1 Description

The Delete-Network request deletes a network from the organisation.

2.3.2.1.2 Requirements

Values of the request: **Network ID** {network}

Objects: none

2.3.2.1.3 Request

To delete a network, add the **Network ID** {network} to the path of the request.

No further information is required.

In response to a successful request, the system returns only the HTTP status code 200.

2.3.2.1.4 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.

STATUS CODE	DESCRIPTION
403	The request has not succeeded because the user does not have the right permissions.

2.3.2.2 Listing all networks with their mitigation status

 The `pps_limit_percentage` and `bw_limit_percentage` attributes are only present if the organisation has percentage thresholds enabled.

 SOC accounts must instead address an organisation explicitly through the `/organisations/{organisation}/networks` endpoint.

Sends a `GET` request to the endpoint `/networks-with-mitigations`.

2.3.2.2.1 Description

The List-Networks-With-Mitigations request returns a list of all networks of the active organisation, including their current mitigation status.

2.3.2.2.2 Requirements

Values of the request: none

Objects: none

2.3.2.2.3 Request

To request a list of all networks with their mitigation status, no additional information is required in the path of the request.

As a result, the user gets one or more objects `NetworkV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The ID of the network.	<code>string</code>

Attributes	Description	Values
organisation	The associated organisation.	object
name	The name of the network.	string
cidr	The CIDR of the network.	string
enabled	Shows whether automatic mitigation is enabled.	true false
data_only	Shows that the network is a monitor-only network: visible in the dashboard, but cannot be mitigated.	true false
mitigation_type	The mitigation type of the network.	ACTION_BLACKHOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
auto_mitigation_strategy	The automatic mitigation strategy of the network.	string
duration	The duration of the automatic mitigation.	integer
subnet_mitigation_override	The mitigation override for the subnet.	true false
pps_limit	The configured limit for packets per second.	integer
bw_limit	The configured bandwidth limit.	integer
autoStatus	Shows whether the network is currently in automatic mitigation.	true false
manualStatus	Shows whether the network is currently in manual mitigation.	true false
active_partial_manual_mitigations	The active partial manual mitigations.	array

Attributes	Description	Values
active_partial_auto_mitigations	The active partial automatic mitigations.	array
allow_manual_mitigation	Shows whether manual mitigations can be started for the network.	true false
extra	Additional custom fields of the organisation.	object

2.3.2.2.4 Example

Example response:

```
{
  "data": [
    {
      "id": "xY9pQ5wR1",
      "organisation": {
        "id": "aB3cD4eF5",
        "name": "ACME GmbH"
      },
      "name": "Customer-A-Prod",
      "cidr": "192.0.2.0/24",
      "enabled": true,
      "data_only": false,
      "mitigation_type": "ACTION_BLACKHOLE",
      "auto_mitigation_strategy": "IP",
      "duration": 0,
      "subnet_mitigation_override": false,
      "pps_limit": 0,
      "bw_limit": 0,
      "autoStatus": true,
      "manualStatus": true,
      "active_partial_manual_mitigations": [
        {}
      ],
      "active_partial_auto_mitigations": [
        {}
      ],
      "allow_manual_mitigation": true,
      "extra": {}
    }
  ],
  "links": {
    "first": "https://datahub-api.com/api/networks?page=1",
    "last": "https://datahub-api.com/api/networks?page=5",
    "prev": null,
    "next": "https://datahub-api.com/api/networks?page=2"
  }
},
```

```

"meta": {
  "current_page": 1,
  "from": 1,
  "last_page": 5,
  "links": [
    {
      "url": "https://datahub-api.com/api/networks?page=2",
      "label": "Next »",
      "active": false
    }
  ],
  "path": "https://datahub-api.com/api/networks",
  "per_page": 15,
  "to": 15,
  "total": 64
}

```

2.3.2.2.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.2.3 Listing all networks of the organisation



SOC accounts must instead address an organisation explicitly through the `/organisations/{organisation}/networks` endpoint.

Sends a `GET` request to the endpoint `/networks`.

2.3.2.3.1 Description

The List-Networks request returns a list of all networks of the organisation.

2.3.2.3.2 Requirements

Values of the request: none

Objects: none

2.3.2.3.3 Request

To request a list of all networks, no additional information is required in the path of the request.

As a result, the user gets one or more objects `NetworkV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the network.	string
organisation	The associated organisation, referenced by <code>id</code> and <code>name</code> .	object
name	The name of the network.	string
cidr	The IP range of the network in CIDR notation.	string
enabled	Defines whether automatic mitigation is enabled.	true false
data_only	Defines whether the network is monitored only: visible in the dashboard, but cannot be mitigated.	true false
mitigation_type	The type of mitigation applied when the thresholds are exceeded.	ACTION_BLACKHOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
auto_mitigation_strategy	The strategy for the automatic mitigation.	string
duration		integer

Attributes	Description	Values
	The duration of the automatic mitigation in seconds.	
subnet_mitigation_override	Defines whether the subnet size restriction is overridden.	true false
pps_limit	The configured PPS limit.	integer
bw_limit	The configured bandwidth limit.	integer
autoStatus	Shows whether the network is currently in automatic mitigation.	true false
manualStatus	Shows whether the network is currently in manual mitigation.	true false
active_partial_manual_mitigations	The active partial manual mitigations of the network.	array
active_partial_auto_mitigations	The active partial automatic mitigations of the network.	array
allow_manual_mitigation	Shows whether manual mitigations can be started for the network.	true false
extra	Additional custom fields of the organisation.	object

2.3.2.3.4 Example

Example response:

```
{
  "data": [
    {
      "id": "xY9pQ5wR1",
      "organisation": {
        "id": "aB3cD4eF5",
        "name": "ACME GmbH"
      },
      "name": "Customer-A-Prod",
      "cidr": "192.0.2.0/24",
      "enabled": true,
      "data_only": false,
      "mitigation_type": "ACTION_BLACKHOLE",
    }
  ]
}
```

```

    "auto_mitigation_strategy": "IP",
    "duration": 0,
    "subnet_mitigation_override": false,
    "pps_limit": 0,
    "bw_limit": 0,
    "autoStatus": true,
    "manualStatus": true,
    "active_partial_manual_mitigations": [
      {}
    ],
    "active_partial_auto_mitigations": [
      {}
    ],
    "allow_manual_mitigation": true,
    "extra": {}
  }
],
"links": {
  "first": "https://datahub-api.com/api/networks?page=1",
  "last": "https://datahub-api.com/api/networks?page=5",
  "prev": null,
  "next": "https://datahub-api.com/api/networks?page=2"
},
"meta": {
  "current_page": 1,
  "from": 1,
  "last_page": 5,
  "links": [
    {
      "url": "https://datahub-api.com/api/networks?page=2",
      "label": "Next »",
      "active": false
    }
  ],
  "path": "https://datahub-api.com/api/networks",
  "per_page": 15,
  "to": 15,
  "total": 64
}
}

```

2.3.2.3.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	

STATUS CODE	DESCRIPTION
	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.2.4 Getting a network by ID



The `pps_limit_percentage` and `bw_limit_percentage` attributes are only present if the organisation has percentage thresholds enabled.



SOC accounts must instead address an organisation explicitly through the `/organisations/{organisation}/networks` endpoint.

Sends a `GET` request to the endpoint `/networks/{network}`.

2.3.2.4.1 Description

The Get-Network request returns a single network for a specified ID.

2.3.2.4.2 Requirements

Values of the request: **Network ID** `{network}`

Objects: none

2.3.2.4.3 Request

To request a single network, add the **Network ID** `{network}` to the path of the request.

As a result, the user gets an object `NetworkV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The ID of the network.	<code>string</code>

Attributes	Description	Values
organisation	The associated organisation.	object
name	The name of the network.	string
cidr	The CIDR range of the network.	string
enabled	Defines whether automatic mitigation is enabled.	true false
data_only	Defines whether the network is monitored only: visible in the dashboard, but cannot be mitigated.	true false
mitigation_type	The mitigation type of the network.	ACTION_BLACKHOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
auto_mitigation_strategy	The automatic mitigation strategy of the network.	string
duration	The duration of the automatic mitigation.	integer
subnet_mitigation_override	The mitigation override for the subnet.	true false
pps_limit	The configured PPS limit.	integer
bw_limit	The configured bandwidth limit.	integer
autoStatus	Defines whether an automatic mitigation is currently running for the network.	true false
manualStatus	Defines whether a manual mitigation is currently running for the network.	true false
active_partial_manual_mitigations	The active partial manual mitigations.	array

Attributes	Description	Values
active_partial_auto_mitigations	The active partial automatic mitigations.	array
allow_manual_mitigation	Shows whether manual mitigations can be started for the network.	true false
extra	Additional custom fields of the organisation.	object

2.3.2.4.4 Example

Example response:

```
{
  "id": "xY9pQ5wR1",
  "organisation": {
    "id": "aB3cD4eF5",
    "name": "ACME GmbH"
  },
  "name": "Customer-A-Prod",
  "cidr": "192.0.2.0/24",
  "enabled": true,
  "data_only": false,
  "mitigation_type": "ACTION_BLACKHOLE",
  "auto_mitigation_strategy": "IP",
  "duration": 0,
  "subnet_mitigation_override": false,
  "pps_limit": 0,
  "bw_limit": 0,
  "autoStatus": true,
  "manualStatus": true,
  "active_partial_manual_mitigations": [
    {}
  ],
  "active_partial_auto_mitigations": [
    {}
  ],
  "allow_manual_mitigation": true,
  "extra": {}
}
```

2.3.2.4.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.2.5 Listing all mitigations of a network



The threshold and traffic values — `configured_bw`, `configured_pps`, `configured_bw_percentage`, `configured_pps_percentage`, `actual_bw`, `actual_pps`, `peak_bw`, `peak_pps`, `total_bw`, `total_pps` and (if the dropped data report function is enabled) `dropped_bits` and `dropped_packets` — are only returned for automatic mitigations triggered by detection. They are omitted for manual mitigations, which contain no detection data.



SOC accounts must instead address an organisation explicitly through the `/organisations/{organisation}/mitigations` endpoint.

Sends a `GET` request to the endpoint `/networks/{network}/mitigations`.

2.3.2.5.1 Description

The List-Network-Mitigations request returns a list of all mitigations of a specified network.

2.3.2.5.2 Requirements

Values of the request: **Network ID** `{network}`

Objects: none

2.3.2.5.3 Request

To request a list of all mitigations of a network, add the **Network ID** {network} to the path of the request.

As a result, the user gets one or more objects `MitigationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the mitigation.	string
organisation	The associated organisation.	object
network	The network or, in the case of a partial mitigation, the specific IP that is mitigated.	string
mitigation_type	The type of the mitigation.	ACTION_BLACKHOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
mitigation_cause	The way in which the mitigation was triggered.	MANUAL_TRIGGER AUTO_TRIGGER OPS_TRIGGER UNKNOWN_TRIGGER
start	The start date of the mitigation in ISO 8601 format.	string(\$date-time)
end	The end date of the mitigation in ISO 8601 format.	string(\$date-time)
created_at	The creation date in ISO 8601 format.	string(\$date-time)
updated_at	The last modification date in ISO 8601 format.	string(\$date-time)

Attributes	Description	Values
actual_bw	The actual bandwidth of the mitigation.	number(\$float)
actual_pps	The actual packets per second of the mitigation.	number(\$float)
configured_bw	The configured bandwidth of the mitigation.	number(\$float)
configured_pps	The configured packets per second of the mitigation.	number(\$float)
configured_bw_percentage	The configured bandwidth as a percentage.	number
configured_pps_percentage	The configured packets per second as a percentage.	number
peak_bw	The peak bandwidth of the mitigation.	number(\$float)
peak_pps	The maximum packets per second of the mitigation.	number(\$float)
total_bw	The total bandwidth of the mitigation.	number(\$float)
total_pps	The total packets per second of the mitigation.	number(\$float)
has_report	Shows whether a report is available for the mitigation.	true false
start_user	The users who started the mitigation.	object
end_user	The users who ended the mitigation. This value is null while the mitigation is running.	object

2.3.2.5.4 Example

Example response:

```
{
  "data": [
    {
      "id": "xY9pQ5wR1",
      "organisation": {
        "id": "aB3cD4eF5",
```

```

    "name": "ACME GmbH"
  },
  "network": "192.0.2.0/24",
  "mitigation_type": "ACTION_MITIGATE_ONPREM",
  "mitigation_cause": "MANUAL_TRIGGER",
  "start": "2026-01-01T00:00:00+00:00",
  "end": "2026-01-01T00:00:00+00:00",
  "created_at": "2026-01-01T00:00:00+00:00",
  "updated_at": "2026-01-01T00:00:00+00:00",
  "actual_bw": 0,
  "actual_pps": 0,
  "configured_bw": 0,
  "configured_pps": 0,
  "configured_bw_percentage": 0,
  "configured_pps_percentage": 0,
  "peak_bw": 0,
  "peak_pps": 0,
  "total_bw": 0,
  "total_pps": 0,
  "has_report": true,
  "start_user": {
    "id": "pQ7rS8tU9",
    "name": "Max Mustermann"
  },
  "end_user": {
    "id": "pQ7rS8tU9",
    "name": "Max Mustermann"
  }
}
],
"links": {
  "first": "https://datahub-api.com/api/networks?page=1",
  "last": "https://datahub-api.com/api/networks?page=5",
  "prev": null,
  "next": "https://datahub-api.com/api/networks?page=2"
},
"meta": {
  "current_page": 1,
  "from": 1,
  "last_page": 5,
  "links": [
    {
      "url": "https://datahub-api.com/api/networks?page=2",
      "label": "Next »",
      "active": false
    }
  ]
},
"path": "https://datahub-api.com/api/networks",
"per_page": 15,
"to": 15,
"total": 64
}
}

```

2.3.2.5.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.2.6 Changing the settings of a network



The body must contain the `id` and `modified` attributes in order to identify the corresponding entry.



The ID of the entry in the request path must match the value of the `id` attribute in the body.



The `pps_limit` and `pps_limit_percentage` attributes are mutually exclusive; the same applies to `bw_limit` and `bw_limit_percentage`.



The `enabled` status and the `subnet_mitigation_override` attribute cannot be changed while an active mitigation is running for the network.



This request is available to SOC users only.

Sends a `PATCH` request to the endpoint `/networks/{network}`.

2.3.2.6.1 Description

The Change-Network request changes the settings of a network of the organisation.

2.3.2.6.2 Requirements

Values of the request: **Network ID** {network}

Objects: NetworkV0

2.3.2.6.3 Request

To change the settings of a network, add the **Network ID** {network} to the path of the request.

For a detailed specification of which information is required to change the settings of a network, an object `NetworkV0` with the following attributes must be defined in the body:

Attribute	Description	Values
id	The ID of the network.	string
modified	The last modification date in ISO 8601 format.	string(\$date-time)
cidr	The CIDR range of the network.	string
enabled	Defines whether automatic mitigation is enabled for the network. If false, no automatic mitigations can be triggered; manual mitigations and ops mitigations are not affected.	true false
pps_limit	The PPS threshold.	integer
bw_limit	The bandwidth threshold in Mbps.	integer

The following attributes are optional:

Attributes	Description	Values
name	The name of the network.	

Attributes	Description	Values
		string
pps_limit_calculated	The calculated PPS threshold.	integer
bw_limit_calculated	The calculated bandwidth threshold.	integer
team_id	The ID of the organisation to which this network belongs.	string
autoStatus	Defines whether an automatic mitigation is currently running for the network.	true false
manualStatus	Defines whether a manual mitigation is currently running for the network.	true false
active_partial_mitigations	The active partial manual mitigations.	array
active_partial_auto_mitigations	The active partial automatic mitigations.	array
country_blocks	The active country blocks.	array
data_only	If true, the network is shown in the dashboard for monitoring only and cannot be mitigated.	true false
subnet_mitigation_override	Defines whether the subnet size restriction is overridden for cloud or hybrid mitigation.	true false
extra	Additional information about the network.	object

Attributes	Description	Values
mitigation_type	The configured mitigation type.	string
emails	The email addresses for notifications.	array
duration	The default mitigation duration in seconds.	integer
auto_mitigation_strategy	The strategy used for automatic mitigations.	string

As a result, the user gets an object `NetworkV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the network.	string
name	The name of the network.	string
cidr	The CIDR range of the network.	string
enabled	Defines whether automatic mitigation is enabled for the network. If false, no automatic mitigations can be triggered; manual mitigations and ops mitigations are not affected.	true false
pps_limit	The PPS threshold.	integer
bw_limit	The bandwidth threshold in Mbps.	integer
pps_limit_calculated	The calculated PPS threshold.	integer

The calculated bandwidth threshold.

Attributes	Description	Values
bw_limit_calculated		integer
team_id	The ID of the organisation to which this network belongs.	string
autoStatus	Defines whether an automatic mitigation is currently running for the network.	true false
manualStatus	Defines whether a manual mitigation is currently running for the network.	true false
active_partial_mitigations	The active partial manual mitigations.	array
active_partial_auto_mitigations	The active partial automatic mitigations.	array
country_blocks	The active country blocks.	array
data_only	If true, the network is shown in the dashboard for monitoring only and cannot be mitigated.	true false
extra	Additional information about the network.	object
mitigation_type	The configured mitigation type.	string
emails	The email addresses for notifications.	array
duration	The default mitigation duration in seconds.	

Attributes	Description	Values
		integer
auto_mitigation_strategy	The strategy used for automatic mitigations.	string

2.3.2.6.4 Example

Example request body:

```
{
  "name": "Production Network",
  "cidr": "127.0.0.1/32",
  "enabled": true,
  "pps_limit": 1000,
  "bw_limit": 200,
  "pps_limit_calculated": 800,
  "bw_limit_calculated": 160,
  "team_id": "xY9pQ5wR1",
  "autoStatus": false,
  "manualStatus": false,
  "active_partial_mitigations": [
    {}
  ],
  "active_partial_auto_mitigations": [
    {}
  ],
  "country_blocks": [
    {}
  ],
  "data_only": false,
  "allow_manual_mitigation": true,
  "extra": {},
  "mitigation_type": "string",
  "emails": [
    "string"
  ],
  "duration": 3600,
  "auto_mitigation_strategy": "ip"
}
```

2.3.2.6.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.2.7 Adding a network to the organisation



The body does not contain the `id` , `created` , and `modified` attributes. The system sets these values after the entry has been created.



The `pps_limit` and `pps_limit_percentage` attributes are mutually exclusive; the same applies to `bw_limit` and `bw_limit_percentage` .



For `ACTION_MITIGATE_CLOUD` , IPv4 networks require at least /24 and IPv6 networks at least /48.



This request is available to SOC users only.

Sends a `POST` request to the endpoint `/networks` .

2.3.2.7.1 Description

The Add-Network request adds a new network to the organisation.

2.3.2.7.2 Requirements

Values of the request: none

Objects: NetworkV0

2.3.2.7.3 Request

To add a network, no additional information is required in the path of the request.

For a detailed specification of which information is required to add a network, an object `NetworkV0` with the following attributes must be defined in the body:

Attributes	Description	Values
<code>cidr</code>	The IP range in CIDR notation. Must be unique within the organisation.	string
<code>enabled</code>	Defines whether automatic mitigation is enabled for the network. If <code>false</code> , no automatic mitigations are triggered; manual and ops mitigations are not affected.	true false
<code>pps_limit</code>	The absolute PPS threshold. Required if <code>pps_limit_percentage</code> is not specified.	integer
<code>bw_limit</code>	The absolute bandwidth threshold in Mbps. Required if <code>bw_limit_percentage</code> is not specified.	integer

The following attributes are optional:

Attributes	Description	Values
<code>name</code>	The name of the network.	string
<code>team_id</code>	The ID of the organisation to which the network is added.	string
<code>pps_limit_calculated</code>	The calculated PPS threshold.	integer
	The calculated bandwidth threshold.	integer

Attributes	Description	Values
bw_limit_calculated		
autoStatus	Shows whether the network is currently in automatic mitigation.	true false
manualStatus	Shows whether the network is currently in manual mitigation.	true false
active_partial_mitigations	The active partial manual mitigations.	array
active_partial_auto_mitigations	The active partial automatic mitigations.	array
country_blocks	The active country blocks.	array
data_only	If true, the network is shown in the dashboard for monitoring only and cannot be mitigated.	true false
allow_manual_mitigation	Shows whether manual mitigations can be started for the network. The default value is true if the attribute is missing.	true false
subnet_mitigation_override	Defines whether the subnet size restriction is overridden for cloud or hybrid mitigation.	true false
extra	Additional custom fields of the organisation.	object
mitigation_type	The mitigation type to apply.	ACTION_BLOCKHOLE ACTION_MITIGATE_ON_PREM ACTION_MITIGATE_CLOUD
emails		array

Attributes	Description	Values
	The email addresses that are notified when a mitigation starts or ends.	
duration	The maximum mitigation duration in seconds (minimum 300).	integer
auto_mitigation_strategy	The strategy for the automatic mitigation.	IP CIDR INTERNET DEFAULT

In response, the system returns the object `NetworkV0` with the information about the new network.

The object provides the following information:

Attributes	Description	Values
message	The status message of the request.	string
network	The newly created network as a <code>NetworkV0</code> object.	object

2.3.2.7.4 Example

Example request body:

```
{
  "name": "Production Network",
  "cidr": "127.0.0.1/32",
  "enabled": true,
  "pps_limit": 1000,
  "bw_limit": 200,
  "pps_limit_calculated": 800,
  "bw_limit_calculated": 160,
  "team_id": "xY9pQ5wR1",
  "autoStatus": false,
  "manualStatus": false,
  "active_partial_mitigations": [
    {}
  ],
  "active_partial_auto_mitigations": [
    {}
  ],
  "country_blocks": [
    {}
  ]
}
```

```

    ],
    "data_only": false,
    "allow_manual_mitigation": true,
    "extra": {},
    "mitigation_type": "string",
    "emails": [
        "string"
    ],
    "duration": 3600,
    "auto_mitigation_strategy": "ip"
}

```

2.3.2.7.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.2.8 Starting a manual mitigation for a network



If a manual mitigation is already active for the network, a second one cannot be started. The existing mitigation must be stopped first. Data-only networks cannot be mitigated.



A partial mitigation cannot be started for a single-host network (an IPv4 / 32 or IPv6 / 128), because it covers only a single address. Omit `ip` to mitigate the entire network instead.

Sends a `POST` request to the endpoint `/networks/{network}/mitigation/start`.

2.3.2.8.1 Description

The Start-Manual-Mitigation request starts a manual mitigation for a specified network.

2.3.2.8.2 Requirements

Values of the request: **Network ID** {network}

Objects: none

2.3.2.8.3 Request

To start a manual mitigation, add the **Network ID** {network} to the path of the request.

The body requires no attributes. The following attributes are optional:

Attribute	Description	Values
ip	A list of individual IPs within the network for a partial mitigation. If this information is missing, the entire network CIDR is mitigated. Both IPv4 and IPv6 are accepted.	array

As a result, the user gets one or more objects `MitigationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the mitigation.	string
organisation	The associated organisation.	object
network	The network, or the specific IP that is mitigated in the case of a partial mitigation.	string
mitigation_type	The type of the mitigation.	ACTION_BLACK_HOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD

Attributes	Description	Values
mitigation_cause	How the mitigation was triggered.	MANUAL_TRIGGER AUTO_TRIGGER OPS_TRIGGER UNKNOWN_TRIGGER
start	The start date of the mitigation in ISO 8601 format.	string(\$date-time)
end	The end date of the mitigation in ISO 8601 format.	string(\$date-time)
created_at	The creation date in ISO 8601 format.	string(\$date-time)
updated_at	The last modification date in ISO 8601 format.	string(\$date-time)
actual_bw	The actual bandwidth.	number(\$float)
actual_pps	The actual packets per second.	number(\$float)
configured_bw	The configured bandwidth.	number(\$float)
configured_pps	The configured packets per second.	number(\$float)
configured_bw_percentage	The configured bandwidth as a percentage.	number
configured_pps_percentage	The configured packets per second as a percentage.	number
peak_bw	The peak bandwidth.	number(\$float)
peak_pps	The maximum packets per second.	number(\$float)
total_bw	The total bandwidth.	number(\$float)
total_pps	The total packets per second.	number(\$float)
has_report	Shows whether a report is available for the mitigation.	true false

Attributes	Description	Values
start_user	The person who started the mitigation.	object
end_user	The person who ended the mitigation. This value is null while the mitigation is running.	object

2.3.2.8.4 Example

Example request body:

```
{
  "ip": [
    "192.0.2.1"
  ]
}
```

2.3.2.8.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
304	The resource has not changed since the last request.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.2.9 Stopping the active manual mitigation of a network

Sends a POST request to the endpoint `/networks/{network}/mitigation/stop`.

2.3.2.9.1 Description

The Stop-Mitigation request stops the active manual mitigation for a specified network.

2.3.2.9.2 Requirements

Values of the request: **Network ID** {network}

Objects: none

2.3.2.9.3 Request

To stop the active manual mitigation, add the **Network ID** {network} to the path of the request.

The following attributes are optional:

Attributes	Description	Values
ip	A list of individual IPs within the network for which the mitigation is to be stopped. If this information is missing, the mitigation is stopped for the entire network CIDR.	array

As a result, the user gets one or more objects `MitigationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the mitigation.	string
organisation	The associated organisation.	object
network	The network or, in the case of a partial mitigation, the specific IP that is mitigated.	string
mitigation_type	The type of the mitigation.	ACTION_BLACKHOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD

Attributes	Description	Values
mitigation_cause	How the mitigation was triggered.	MANUAL_TRIGGER AUTO_TRIGGER OPS_TRIGGER UNKNOWN_TRIGGER
start	The start date of the mitigation in ISO 8601 format.	string(\$date-time)
end	The end date of the mitigation in ISO 8601 format.	string(\$date-time)
created_at	The creation date in ISO 8601 format.	string(\$date-time)
updated_at	The last modification date in ISO 8601 format.	string(\$date-time)
actual_bw	The actual bandwidth.	number(\$float)
actual_pps	The actual packets per second.	number(\$float)
configured_bw	The configured bandwidth.	number(\$float)
configured_pps	The configured packets per second.	number(\$float)
configured_bw_percentage	The configured bandwidth as a percentage.	number
configured_pps_percentage	The configured packets per second as a percentage.	number
peak_bw	The peak bandwidth.	number(\$float)
peak_pps	The maximum packets per second.	number(\$float)
total_bw	The total bandwidth.	number(\$float)
total_pps	The total packets per second.	number(\$float)
has_report	Whether a report is available for the mitigation.	true false

Attributes	Description	Values
start_user	The users who started the mitigation.	object
end_user	The users who ended the mitigation; null while the mitigation is running.	object

2.3.2.9.4 Example

Example request body:

```
{
  "ip": [
    "string"
  ]
}
```

2.3.2.9.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
304	The resource has not changed since the last request.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.2.10 Triggering a resync of the networks of the organisation



SOC accounts cannot call this endpoint with a personal access token. There is no organisation-related token equivalent for this. Use the access options provided by the web application (session authentication) instead.

Sends a `POST` request to the endpoint `/networks/resync`.

2.3.2.10.1 Description

The Resync-Networks request publishes a message to resynchronise the networks of the current organisation, as if a network had been edited.

2.3.2.10.2 Requirements

Values of the request: none

Objects: none

2.3.2.10.3 Request

To resynchronise the networks, no additional information is required in the path of the request. A request body is not required.

As a result, the user gets an object with a confirmation message.

The object provides the following information:

Attribute	Description	Values
message	The confirmation message returned after the resync is triggered.	string

2.3.2.10.4 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.

STATUS CODE	DESCRIPTION
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
503	The request was unsuccessful because the service is temporarily unavailable.

2.3.3 Mitigations

2.3.3.1 Listing all mitigations of the organisation



The threshold and traffic metrics — `configured_bw`, `configured_pps`, `configured_bw_percentage`, `configured_pps_percentage`, `actual_bw`, `actual_pps`, `peak_bw`, `peak_pps`, `total_bw`, `total_pps` and (if the dropped data report function is enabled) `dropped_bits` and `dropped_packets` — are only returned for automatic mitigations triggered by detection. They are omitted for manual mitigations, which contain no detection data.



SOC accounts must instead address an organisation explicitly through the `/organisations/{organisation}/mitigations` endpoint.

Sends a `GET` request to the endpoint `/mitigations`.

2.3.3.1.1 Description

The List-Mitigations request returns a list of all mitigations of the organisation.

2.3.3.1.2 Requirements

Values of the request: none

Objects: none

2.3.3.1.3 Request

To request a list of all mitigations, no additional information is required in the path of the request.

As a result, the user gets one or more objects `MitigationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The ID of the mitigation.	string

Attributes	Description	Values
organisation	The associated organisation.	object
network	The mitigated network, or a single IP address in the case of a partial mitigation.	string
mitigation_type	The type of the applied mitigation.	ACTION_BLACKHOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
mitigation_cause	How the mitigation was triggered.	MANUAL_TRIGGER AUTO_TRIGGER OPS_TRIGGER UNKNOWN_TRIGGER
start	When the mitigation started.	string(\$date-time)
end	When the mitigation ended; null while it is still running.	string(\$date-time)
created_at	The creation date of the entry in ISO 8601 format.	string(\$date-time)
updated_at	The date of the last update of the entry in ISO 8601 format.	string(\$date-time)
actual_bw	The measured bandwidth at the start of the mitigation.	number(\$float)
actual_pps	The measured packet rate at the start of the mitigation.	number(\$float)
configured_bw	The bandwidth threshold configured at the start of the mitigation.	number(\$float)
configured_pps	The packet rate threshold configured at the start of the mitigation.	number(\$float)

Attributes	Description	Values
configured_bw_percentage	The bandwidth threshold as a percentage of the calculated baseline.	number
configured_pps_percentage	The packet rate threshold as a percentage of the calculated baseline.	number
peak_bw	The peak bandwidth observed during the mitigation.	number(\$float)
peak_pps	The peak packet rate observed during the mitigation.	number(\$float)
total_bw	The total bits processed during the mitigation.	number(\$float)
total_pps	The total packets processed during the mitigation.	number(\$float)
has_report	Defines whether a detailed mitigation report is available.	true false
start_user	Who started the mitigation.	object
end_user	Who ended the mitigation; null while it is still running.	object

2.3.3.1.4 Example

Example response:

```
{
  "data": [
    {
      "id": "xY9pQ5wR1",
      "organisation": {
        "id": "aB3cD4eF5",
        "name": "ACME GmbH"
      },
      "network": "192.0.2.0/24",
      "mitigation_type": "ACTION_MITIGATE_ONPREM",
      "mitigation_cause": "MANUAL_TRIGGER",
      "start": "2026-01-01T00:00:00+00:00",
      "end": "2026-01-01T00:00:00+00:00",
      "created_at": "2026-01-01T00:00:00+00:00",
      "updated_at": "2026-01-01T00:00:00+00:00",
    }
  ]
}
```

```
    "actual_bw": 0,
    "actual_pps": 0,
    "configured_bw": 0,
    "configured_pps": 0,
    "configured_bw_percentage": 0,
    "configured_pps_percentage": 0,
    "peak_bw": 0,
    "peak_pps": 0,
    "total_bw": 0,
    "total_pps": 0,
    "has_report": true,
    "start_user": {
      "id": "pQ7rS8tU9",
      "name": "Max Mustermann"
    },
    "end_user": {
      "id": "pQ7rS8tU9",
      "name": "Max Mustermann"
    }
  },
  "links": {
    "first": "https://datahub-api.com/api/networks?page=1",
    "last": "https://datahub-api.com/api/networks?page=5",
    "prev": null,
    "next": "https://datahub-api.com/api/networks?page=2"
  },
  "meta": {
    "current_page": 1,
    "from": 1,
    "last_page": 5,
    "links": [
      {
        "url": "https://datahub-api.com/api/networks?page=2",
        "label": "Next »",
        "active": false
      }
    ],
    "path": "https://datahub-api.com/api/networks",
    "per_page": 15,
    "to": 15,
    "total": 64
  }
}
```

2.3.3.1.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.3.2 Getting a mitigation by ID



The threshold and traffic values — `configured_bw`, `configured_pps`, `configured_bw_percentage`, `configured_pps_percentage`, `actual_bw`, `actual_pps`, `peak_bw`, `peak_pps`, `total_bw`, `total_pps` and (if the dropped data report function is enabled) `dropped_bits` and `dropped_packets` — are only returned for automatic mitigations triggered by detection. They are omitted for manual mitigations, which contain no detection data. You need at least READ permissions for the selected period.



SOC accounts must instead address an organisation explicitly through the `/organisations/{organisation}/mitigations` endpoint.

Sends a GET request to the endpoint `/mitigations/{mitigation}`.

2.3.3.2.1 Description

The Get-Mitigation request returns a single mitigation for a specified ID.

2.3.3.2.2 Requirements

Values of the request: **Mitigation ID** `{mitigation}`

Objects: none

2.3.3.2.3 Request

To request a mitigation, add the **Mitigation ID** {mitigation} to the path of the request.

As a result, the user gets an object `MitigationV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the mitigation.	string
organisation	The associated organisation of the mitigation.	object
network	The network, or the specific IP address that is mitigated in the case of a partial mitigation.	string
mitigation_type	The applied mitigation type.	ACTION_BLACK_HOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
mitigation_cause	How the mitigation was triggered.	MANUAL_TRIGGER AUTO_TRIGGER OPS_TRIGGER UNKNOWN_TRIGGER
start	The start date of the mitigation in ISO 8601 format.	string(\$date-time)
end	The end date of the mitigation in ISO 8601 format.	string(\$date-time)
created_at	The creation date in ISO 8601 format.	string(\$date-time)
updated_at	The last modification date in ISO 8601 format.	string(\$date-time)
actual_bw	The actual bandwidth of the mitigation.	number(\$float)

Attributes	Description	Values
actual_pps	The actual packets per second of the mitigation.	number(\$float)
configured_bw	The configured bandwidth of the mitigation.	number(\$float)
configured_pps	The configured packets per second of the mitigation.	number(\$float)
configured_bw_percentage	The configured bandwidth as a percentage value.	number
configured_pps_percentage	The configured packets per second as a percentage value.	number
peak_bw	The peak bandwidth of the mitigation.	number(\$float)
peak_pps	The peak value of the packets per second of the mitigation.	number(\$float)
total_bw	The total bandwidth of the mitigation.	number(\$float)
total_pps	The total number of packets per second of the mitigation.	number(\$float)
has_report	Shows whether a report is available for the mitigation.	true false
start_user	The user who started the mitigation.	object
end_user	The user who ended the mitigation; null while the mitigation is running.	object
peaks	The breakdown of the peak traffic of the mitigation.	object

2.3.3.2.4 Example

Example response:

```
{
  "id": "string",
  "organisation": {},
  "network": "string",
  "mitigation_type": "ACTION_BLACKHOLE",
```

```

"mitigation_cause": "MANUAL_TRIGGER",
"start": "2026-01-01T00:00:00+00:00",
"end": "2026-01-01T00:00:00+00:00",
"created_at": "2026-01-01T00:00:00+00:00",
"updated_at": "2026-01-01T00:00:00+00:00",
"actual_bw": 0,
"actual_pps": 0,
"configured_bw": 0,
"configured_pps": 0,
"configured_bw_percentage": 0,
"configured_pps_percentage": 0,
"peak_bw": 0,
"peak_pps": 0,
"total_bw": 0,
"total_pps": 0,
"has_report": true,
"start_user": {},
"end_user": {},
"peaks": {}
}

```

2.3.3.2.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.3.3 Getting graph data of a mitigation



SOC accounts cannot call this endpoint with a personal access token. There is no organisation-related token equivalent for it. Use the access options provided by the web application (session authentication) instead.

Sends a GET request to the endpoint `/mitigations/{mitigation}/data/{dataType}/{field}`.

2.3.3.3.1 Description

The Get-Mitigation-Data request returns the graph data for a specific mitigation, filtered by data type and field.

2.3.3.3.2 Requirements

Values of the request: **Mitigation ID** {mitigation} ; **Data type** {dataType} ; **Field** {field}

Objects: none

2.3.3.3.3 Request

To request the graph data of a mitigation, add the **Mitigation ID** {mitigation} , the **Data type** {dataType} , and the **Field** {field} to the path of the request.

Data type {dataType} defines the type of data to retrieve, for example `bandwidth` or `protocol` .

Field {field} defines the field to retrieve, for example `bits` or `packets` .

As a result, the user gets an array of series for a graphical visualisation.

The object provides the following information:

Attributes	Description	Values
name	The name of the series.	string
data	The array of data points of the series. Each point provides the attributes <code>x</code> and <code>y</code> .	array

2.3.3.3.4 Example

Example response:

```
[
  {
    "data": [
      {
        "x": 0,
        "y": 0
      }
    ]
  }
]
```

```
    ],  
    "name": "string"  
  }  
]
```

2.3.3.3.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.3.4 Stopping a manual mitigation by ID

Sends a POST request to the endpoint `/mitigations/{mitigation}/stop`.

2.3.3.4.1 Description

The Stop-Mitigation request stops a specific manual mitigation by its ID.

2.3.3.4.2 Requirements

Values of the request: **Mitigation ID** {mitigation}

Objects: none

2.3.3.4.3 Request

To stop a manual mitigation, add the **Mitigation ID** {mitigation} to the path of the request. No further information is required.

As a result, the user gets an object `MitigationV0` with the information about the stopped mitigation.

The object provides the following information:

Attributes	Description	Values
id	The ID of the mitigation.	string
organisation	The associated organisation.	object
network	The network, or the specific IP that is mitigated in the case of a partial mitigation.	string
mitigation_type	The type of the mitigation.	ACTION_BLACK_HOLE ACTION_MITIGATE_ONPREM ACTION_MITIGATE_CLOUD
mitigation_cause	How the mitigation was triggered.	MANUAL_TRIGGER AUTO_TRIGGER OPS_TRIGGER UNKNOWN_TRIGGER
start	The start date in ISO 8601 format.	string(\$date-time)
end	The end date in ISO 8601 format.	string(\$date-time)
created_at	The creation date in ISO 8601 format.	string(\$date-time)
updated_at	The last modification date in ISO 8601 format.	string(\$date-time)
actual_bw	The actual bandwidth.	number(\$float)
actual_pps	The actual packets per second.	number(\$float)
configured_bw	The configured bandwidth.	number(\$float)
configured_pps	The configured packets per second.	number(\$float)

Attributes	Description	Values
configured_bw_percentage	The configured bandwidth as a percentage.	number
configured_pps_percentage	The configured packets per second as a percentage.	number
peak_bw	The peak bandwidth.	number(\$float)
peak_pps	The maximum packets per second.	number(\$float)
total_bw	The total bandwidth.	number(\$float)
total_pps	The total packets per second.	number(\$float)
has_report	Shows whether a report is available for the mitigation.	true false
start_user	The person who started the mitigation.	object
end_user	The person who ended the mitigation. This value is null while the mitigation is running.	object

2.3.3.4.4 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
304	The resource has not changed since the last request.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.4 Anomalies

2.3.4.1 Listing all anomalies of the organisation



The anomalies feature must be enabled for the organisation. When it is disabled, the endpoint responds with the status code 403.



SOC accounts cannot call this endpoint with a personal access token. Use the access via the web application (session authentication) instead.

Sends a GET request to the endpoint `/anomalies`.

2.3.4.1.1 Description

The List-Anomalies request allows you to request a paginated list of all historical anomalies of the organisation.

2.3.4.1.2 Requirements

Values of the request: none

Objects: none

2.3.4.1.3 Request

To request a list of all anomalies, no additional information needs to be added to the path of the request. To paginate, sort, and filter the list, you can append the following optional query parameters:

Attribute	Description	Values
page	The page to return.	integer , minimum 1 , default 1
perPage	The number of anomalies per page.	integer , 1 to 100 , default 10
orderBy	The attribute to sort by.	

Attributes	Description	Values
		started_at , last_updated_at , ended_at , status , cidr , types , default started_at
orderDir	The sort direction.	asc , desc , default desc
search	The free-text search over the cidr , status , and types attributes.	string
status	Only returns anomalies with this status.	OPEN , UPDATE , CLOSED
type	Only returns anomalies that contain this type.	VOLUMETRIC , PROTOCOL , AMPLIFICATION

As a result, you get one or more objects `AnomalyV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The ID of the anomaly.	string
cidr	The network or single IP address affected by the anomaly, in CIDR notation.	string
types	The detected anomaly types. An anomaly can carry more than one type.	VOLUMETRIC , PROTOCOL , AMPLIFICATION
status	The status of the anomaly.	OPEN , UPDATE , CLOSED
started_at	The date and time when the anomaly started in ISO 8601 format.	string(\$date-time)
last_updated_at	The date and time when the anomaly was last updated in ISO 8601 format.	string(\$date-time)

Attributes	Description	Values
ended_at	The date and time when the anomaly ended in ISO 8601 format. While the anomaly is ongoing, the value is <code>null</code> .	<code>string(\$date-time)</code>
metadata	Additional details about the anomaly, provided as a list of key-value entries.	array



Metadata entries flagged as private by the detecting system are never returned. The `metadata` attribute only contains public entries.

2.3.4.1.4 Example

Example response:

```
{
  "data": [
    {
      "id": "aB3xY9",
      "cidr": "203.0.113.0/24",
      "types": [
        "VOLUMETRIC"
      ],
      "status": "OPEN",
      "started_at": "2026-01-01T00:00:00+00:00",
      "last_updated_at": "2026-01-01T00:15:00+00:00",
      "ended_at": null,
      "metadata": [
        {
          "key": "attack_vector",
          "value": "UDP_Reflection"
        }
      ]
    }
  ]
}
```

2.3.4.1.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

2.3.5 Mitigation reports

2.3.5.1 Listing mitigation statistics for a month



This request is available to super admin users only.

Sends a GET request to the endpoint `/mitigation-statistic-group/{group}`.

2.3.5.1.1 Description

The Get-Mitigation-Statistics request returns the mitigation statistics for a specified month of the organisation.

2.3.5.1.2 Requirements

Values of the request: **Month** {group}

Objects: none

2.3.5.1.3 Request

To request the mitigation statistics, add the **Month** {group} (in the format YYYY-MM) to the path of the request.

As a result, the user gets one or more objects `MitigationStatisticV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
org	The name of the organisation.	string
network	The IP address or the CIDR of the mitigated network.	string
start	The date and time of the start of the mitigation, in ISO 8601 format.	string(\$date-time)
end	The date and time of the end of the mitigation, in ISO 8601 format.	string(\$date-time)
trigger		1

Attributes	Description	Values
	The trigger type of the mitigation: 1 started manually, 2 started automatically, 3 started by operations.	2 3
actual_bw	The measured bandwidth in Mbps at the start of the mitigation.	integer
configured_bw	The configured bandwidth threshold in Mbps.	integer
actual_pps	The measured packets per second at the start of the mitigation.	integer
configured_pps	The configured packet rate threshold.	integer
peak_bw	The peak bandwidth observed during the mitigation, in Mbps.	integer
peak_pps	The peak packet rate observed during the mitigation.	integer
total_bw	The total bandwidth received during the mitigation, in bits.	integer
total_pps	The total packets received during the mitigation.	integer
dropped_bits	The total bits dropped by the mitigation.	integer
dropped_packets	The total packets dropped by the mitigation.	integer

2.3.5.1.4 Example

Example response:

```
{
  "data": [
    {
      "org": "Test Organisation",
      "network": "172.0.0.1",
      "start": "2026-01-01T00:00:00+00:00",
```

```

    "end": "2026-01-01T00:00:00+00:00",
    "trigger": 1,
    "actual_bw": 100,
    "configured_bw": 200,
    "actual_pps": 1500,
    "configured_pps": 2000,
    "peak_bw": 400,
    "peak_pps": 3000,
    "total_bw": 123456,
    "total_pps": 78910,
    "dropped_bits": 10000,
    "dropped_packets": 2000
  }
],
"links": {
  "first": "https://datahub-api.com/api/networks?page=1",
  "last": "https://datahub-api.com/api/networks?page=5",
  "prev": null,
  "next": "https://datahub-api.com/api/networks?page=2"
},
"meta": {
  "current_page": 1,
  "from": 1,
  "last_page": 5,
  "links": [
    {
      "url": "https://datahub-api.com/api/networks?page=2",
      "label": "Next »",
      "active": false
    }
  ]
},
"path": "https://datahub-api.com/api/networks",
"per_page": 15,
"to": 15,
"total": 64
}

```

2.3.5.1.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.

STATUS CODE	DESCRIPTION
403	The request has not succeeded because the user does not have the right permissions.

2.3.5.2 Listing all months with mitigation statistics



This endpoint is available to super admin users only.

Sends a GET request to the endpoint `/mitigation-statistic-groups`.

2.3.5.2.1 Description

The List-Mitigation-Statistic-Groups request returns a paginated list of all months for which mitigation statistics of the organisation are available.

2.3.5.2.2 Requirements

Values of the request: none

Objects: none

2.3.5.2.3 Request

To request a list of all months with mitigation statistics, no additional information is required in the path of the request.

As a result, the user gets one or more objects `MitigationStatisticGroupV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The month identifier of the entry in the format <code>YYYY-MM</code> .	string

2.3.5.2.4 Example

Example response:

```
{
  "data": [
    {
      "id": "2026-02"
    }
  ],
  "meta": {
    "current_page": 0,
    "last_page": 0,
    "per_page": 0,
    "total": 0
  }
}
```

2.3.5.2.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.6 Traffic Reports

2.3.6.1 Listing all months with traffic report data



This endpoint is only available to organisations with traffic reports enabled and requires admin-level access.



SOC accounts cannot call this endpoint with a personal access token. There is no organisation-related token equivalent for it. Use the access options provided by the web application (session authentication) instead.

Sends a GET request to the endpoint `/traffic-report-groups`.

2.3.6.1.1 Description

The List-Traffic-Report-Groups request returns a list of all months for which traffic report data is available for the active organisation.

2.3.6.1.2 Requirements

Values of the request: none

Objects: none

2.3.6.1.3 Request

To request a list of all months with traffic report data, no additional information is required in the path of the request.

As a result, the user gets one or more objects with the requested information.

The object provides the following information:

Attributes	Description	Values
id	The month identifier in the format YYYY-MM .	string

2.3.6.1.4 Example

Example response:

```
{
  "data": [
    {
      "id": "2026-04"
    }
  ]
}
```

2.3.6.1.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.6.2 Getting a traffic report for a type and period



This endpoint is only available to organisations with traffic reports enabled and requires admin-level access rights.



SOC accounts cannot call this endpoint with a personal access token. There is no corresponding organisation-related token. Use access through the web application (session authentication) instead.

Sends a GET request to the endpoint `/traffic-reports/{type}/{date}`.

2.3.6.2.1 Description

The Get-Traffic-Report request returns the entries of the traffic report for a specified type and period.

2.3.6.2.2 Requirements

Values of the request: **Report type** {type} ; **Period** {date}

Objects: none

2.3.6.2.3 Request

To request the traffic report, add the **Report type** {type} and the **Period** {date} to the path of the request.

Report type {type} defines the granularity of the report. The following values are available:

Attribute s	Description	Value s
daily	Returns traffic data aggregated by day for the specified month.	
monthly	Returns traffic data aggregated by month for the specified month.	

Period {date} defines the report period. The value must be YYYY-MM-DD for daily granularity and YYYY-MM for monthly granularity.

As a result, the user gets one or more objects `TrafficReportV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
ip	The IP address of the host.	string
cidr	The CIDR block to which the IP address belongs.	string
period_start	The start of the report period in UTC.	string(\$date)

Attributes	Description	Values
period_end	The end of the report period in UTC.	string(\$date)
traffic	The total traffic for the period in bytes.	number(\$float)
packets	The total number of packets for the period.	number(\$float)

2.3.6.2.4 Example

Example response:

```
{
  "data": [
    {
      "ip": "192.0.2.1",
      "cidr": "192.0.2.0/24",
      "period_start": "2026-04-01",
      "period_end": "2026-04-01",
      "traffic": 1234567,
      "packets": 8910
    }
  ],
  "links": {
    "first": "https://datahub-api.com/api/networks?page=1",
    "last": "https://datahub-api.com/api/networks?page=5",
    "prev": null,
    "next": "https://datahub-api.com/api/networks?page=2"
  },
  "meta": {
    "current_page": 1,
    "from": 1,
    "last_page": 5,
    "links": [
      {
        "url": "https://datahub-api.com/api/networks?page=2",
        "label": "Next »",
        "active": false
      }
    ]
  },
  "path": "https://datahub-api.com/api/networks",
  "per_page": 15,
  "to": 15,
  "total": 64
}
```

2.3.6.2.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
404	The request was unsuccessful because the requested resource was not found.

2.3.7 Audit logs

2.3.7.1 Listing all audit log entries of the organisation



SOC accounts cannot call this endpoint with a personal access token. There is no organisation-related token equivalent. Use access through the web application (session authentication) instead.

Sends a `GET` request to the endpoint `/auditLogs`.

2.3.7.1.1 Description

The List-Audit-Logs request returns a list of all audit log entries of the organisation.

2.3.7.1.2 Requirements

Values of the request: none

Objects: none

2.3.7.1.3 Request

To request a list of all audit log entries, no additional information is required in the path of the request.

As a result, the user gets one or more objects `AuditLogV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
event	The type of the logged event.	string
resource	The type of the resource affected by the event.	string
resource_identifier	The identifier of the affected resource.	string
performed_by	The name of the user who performed the action.	string
parameters		object

Attributes	Description	Values
	Additional parameters and details of the logged event.	
created_at	The date and time when the event was logged, in ISO 8601 format.	string(\$date-time)

2.3.7.1.4 Example

Example response:

```
{
  "data": [
    {
      "event": "string",
      "resource": "string",
      "resource_identifier": "string",
      "performed_by": "string",
      "parameters": {},
      "created_at": "2026-01-01T00:00:00+00:00"
    }
  ],
  "links": {
    "first": "https://datahub-api.com/api/networks?page=1",
    "last": "https://datahub-api.com/api/networks?page=5",
    "prev": null,
    "next": "https://datahub-api.com/api/networks?page=2"
  },
  "meta": {
    "current_page": 1,
    "from": 1,
    "last_page": 5,
    "links": [
      {
        "url": "https://datahub-api.com/api/networks?page=2",
        "label": "Next »",
        "active": false
      }
    ]
  },
  "path": "https://datahub-api.com/api/networks",
  "per_page": 15,
  "to": 15,
  "total": 64
}
```

2.3.7.1.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.

2.3.8 User management

2.3.8.1 Getting the account information of the authenticated user

Sends a GET request to the endpoint `/users/me`.

2.3.8.1.1 Description

The Get-Logged-User request returns the account information of the currently authenticated user.

2.3.8.1.2 Requirements

Values of the request: none

Objects: none

2.3.8.1.3 Request

To request the account information of the currently authenticated user, no additional information is required in the path of the request.

As a result, the user gets an object `UserV0` with the requested information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The ID of the user.	string
<code>name</code>	The full name of the user.	string
<code>email</code>	The email address of the user.	string
<code>activeOrganisation</code>	The organisation context in which the token is used.	object

2.3.8.1.4 Example

Example response:

```
{
  "id": "xY9pQ5wR1",
```

```
"name": "Max Mustermann",
"email": "max@mustermann.de",
"activeOrganisation": {
  "id": "xY9pQ5wR1",
  "name": "Test Organisation"
}
}
```

2.3.8.1.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.

2.3.8.2 Changing the notification preference of the authenticated user



The notification preference is only available for an organisation with the anomalies feature enabled, and only for users who are neither a SOC administrator nor a SOC user. SOC administrators and SOC users add their email address to the notification recipient list of the relevant organisation instead.

Sends a PATCH request to the endpoint `/users/me/notification-preferences`.

2.3.8.2.1 Description

The Change-Notification-Preferences request allows you to change the mitigation and anomaly notification email preference of the authenticated user.

2.3.8.2.2 Requirements

Values of the request: none

Objects: NotificationPreferencesV0

2.3.8.2.3 Request

To change the notification preference, no additional information needs to be added to the path of the request.

For a detailed specification of which information is required to change the notification preference, define the object `NotificationPreferencesV0` with the following attributes in the body:

Attributes	Description	Values
<code>notificationsEnabled</code>	Indicates whether the user is opted in to mitigation and anomaly notification emails.	<code>true</code> , <code>false</code>

The system responds by returning the object `ApiUser` with the updated information.

The object provides the following information:

Attributes	Description	Values
<code>id</code>	The ID of the user.	<code>string</code>
<code>name</code>	The full name of the user.	<code>string</code>
<code>email</code>	The email address of the user.	<code>string</code>
<code>notificationsEnabled</code>	Indicates whether the user is opted in to mitigation and anomaly notification emails.	<code>true</code> , <code>false</code>
<code>activeOrganization</code>	The organisation context the token operates in.	<code>object</code>

2.3.8.2.4 Example

Example request body:

```
{
  "notificationsEnabled": true
}
```

2.3.8.2.5 Responses

The following responses are available:

STATUS CODE	DESCRIPTION
200	The request has succeeded.
401	The request has not succeeded because the user authentication was incorrect.
403	The request has not succeeded because the user does not have the right permissions.
422	The request was unsuccessful because the submitted data could not be processed.

3. Troubleshooting

This chapter lists the messages of the Myra DataHub portal, their cause, and how to resolve them.

The portal reports an error in three places:

- **Below the input field** – as long as a value is not valid. The message disappears as soon as the value is correct.
- **As a notification at the edge of the screen** – after an action has failed. It names the action that failed.
- **As a page of its own** – when the application cannot carry out the request at all, for example because a permission is missing.

If the general message **There was an unexpected issue.** appears, the server did not answer the request. Repeat the action. If the message persists, note the time, the view, and the action before you report the error.



The messages appear in the language selected in the portal. This chapter quotes the English wording.

3.1 Login

Login fails

The login screen checks the email address and the password together. It therefore does not state which of the two entries is wrong.

Message	Cause	Remedy
We weren't able to log you in. Please check your login credentials.	The email address or the password is wrong.	Enter both again. Watch the capitalisation of the password and check whether the caps lock key is active.
These credentials do not match our records.	No user account exists for this email address.	Check the spelling of the email address. If the account does not exist yet, ask a person with administration rights to create it.
The provided password is incorrect.	The user account exists, but the password does not belong to it.	Reset the password using Forgot your password?
Too many login attempts. Please try again in n seconds.	Per email address and IP address, 15 login attempts per minute are allowed.	Wait for the time stated. The block ends by itself; a further attempt does not extend it.

The login procedure is described in [Login](#).

Two-factor authentication

Message	Cause	Remedy
The authentication code is not valid.	The code that you entered does not match or is no longer valid.	A code is valid for a short time only. Wait until the authenticator application generates the next code and enter that one. Also check whether the time on the device is correct – a deviating time produces invalid codes.

Message	Cause	Remedy
The provided two factor authentication code was invalid.	The same error when enabling two-factor authentication later on the Profile tab.	Repeat the entry with the next code.
Two-factor authentication is required to use this website.	Two-factor authentication is mandatory for this portal but is not set up for the user account yet.	Set up two-factor authentication. Without it, the portal remains locked.
You have not enabled two-factor authentication.	An action requires two-factor authentication, for example, the display of the recovery codes.	Enable two-factor authentication first.

The second factor is limited as well: after five entries per minute, the portal rejects further attempts. In that case, wait one minute.

If the authenticator application is unavailable – for example, after you changed the device – log in with **Use a recovery code** and one of the emergency recovery codes that you stored during the setup. Each code is valid once. If all codes are used or lost, only a person with administration rights can reset the user account.

Resetting the password

Forgot your password? requests an email containing a reset link.

Message	Cause	Remedy
We have received your request to reset your password. You will receive an email with further instructions shortly.	The portal accepted the request.	Open the link in the email. If the email is missing, check the spam folder.

Message	Cause	Remedy
We can't find a user with that email address.	No user account exists for this email address.	Check the spelling. Use the address the invitation was sent to.
Please wait before retrying.	You made the request too soon after the previous one.	Wait a moment and request the link again.
This password reset token is invalid.	The link expired or someone already used it.	Request a new link and open it immediately after you receive it.
The token has expired. Please restart the process.	The link that activates the account or sets the password expired.	Start the procedure again from the beginning.

The password is not accepted

The new password must meet all of the following rules; if it breaks one, the screen names exactly that rule.

Message	Requirement
The password must be at least 12 characters long.	at least 12 characters
The password must contain at least one lowercase letter.	at least one lowercase letter
The password must contain at least one uppercase letter.	at least one uppercase letter
The password must contain at least one number.	at least one digit
The password must contain at least one of these symbols: !@#\$%^&*.	at least one of the characters !@#\$%^&*
The password is not valid.	

Message	Requirement
	The password does not meet the rules, or it does not match the confirmation.

In addition, the portal checks the password against known data breaches. A password that appears there is rejected even if it meets all rules. Choose a different password in that case.

When you change the password on the **Profile** tab, **Incorrect password. Please try again.** refers to the current password, not to the new one.

3.2 Access and display

The portal shows an error page

If the portal cannot carry out a request, it replaces the view with an error page offering the **Back to dashboard** button.

Page	Message	Cause	Remedy
Access Denied	Sorry, you don't have access to this page.	The user account does not hold the role this view requires, or the view belongs to a different company.	Return to the dashboard. If you need the view for your work, ask a person with administration rights to check your role. Which role opens which view is listed under Roles and permissions .
Page not found	Sorry, the page you are looking for doesn't exist or has been moved.	The address is misspelled, or the object behind it has been deleted – a network whose address is still stored as a bookmark, for example.	Open the view through the navigation instead of through a bookmark.
Internal Server Error	Sorry, an internal server error occurred.	The request failed on the server.	Repeat the action after a short while. If the error persists, note the time and the action and report it.

The session has expired

If an action unexpectedly returns you to the login screen, the session has expired. Without activity, a session ends after 120 minutes by default; the operator of the portal can change this value. Closing the web browser does not end the session.

- ▶ Log in again.
- ▶ Carry out the action once more. Entries you made before the session expired and did not save are lost.



On the **Profile** tab, **Browser sessions** shows which sessions are still open; **Log out other browser sessions** ends them. If you feel your user account has been compromised, end the other sessions and change your password immediately.

A view stays empty

An empty list is not an error: the portal shows only the data of the company you are currently logged in to, and only the selected period.

Message	Meaning	Remedy
No data currently available.	No measurements exist for the selected period.	Select a longer observation period.
No networks found.	No network is assigned to the company.	Ask the SOC to assign the network.
There is no mitigation history.	No mitigation was carried out in the selected period.	Extend the period.
No traffic data found for the selected period.	No traffic report exists for the selected month.	Select a different month.
No reports found.	No mitigation report has been generated yet.	A report is created only after a mitigation has finished.
No audit log found.	No change subject to logging was made in the selected period.	Extend the period or reset the filter.
No anomalies found.	No anomaly was detected in the selected period.	Extend the period.

If a view stays empty although data is expected, first check whether you are logged in to the correct company.

3.3 Networks and mitigations

A manual mitigation cannot be started

Message	Cause	Remedy
Cannot change the manual mitigation setting while there is an ongoing manual mitigation.	A manual mitigation is already running for the network.	End the running mitigation and change the setting afterwards.
This IP address doesn't belong to the selected network.	The IP address entered lies outside the address range of the network.	Enter an address from the range of the network. Leave the field empty to mitigate the entire network.
Invalid ip.	The entry is not a valid IP address.	Enter a complete IPv4 or IPv6 address without spaces.
The network(s) couldn't be mitigated.	The job failed on the server.	Repeat the start after a short while. Before that, check whether a mitigation is already running for the network.

If the **Start mitigation** button is missing entirely, manual mitigation is not enabled for this network, or your user account does not hold administration rights. Only the SOC can change either.

A mitigation cannot be stopped

If the portal reports **The mitigation(s) couldn't be stopped.**, the server did not accept the job. Repeat it after a short while.



Only manually started mitigations can be stopped. A mitigation triggered automatically ends by itself once the attack subsides.

A network cannot be added or edited

The address of a network must be given as a normalised CIDR: the network address followed by the prefix, with no host bits set – for example 192.0.2.0/24 , not 192.0.2.17/24 .

Message	Cause	Remedy
The IP address should be in a normalised CIDR format (IPv4 up to /n, IPv6 up to /n)	The format is wrong, or the prefix is smaller than permitted.	Use the prefix limits stated in the message. They depend on how the installation is connected and are therefore part of the message itself.
For cloud scrubbing, IPv4 must be /24 or smaller, and IPv6 must be /48 or smaller.	The address range entered for a network with cloud scrubbing is too small.	Enter at most a /24 for IPv4 and at most a /48 for IPv6.
An error occurred while adding the network. Please try again shortly.	The server did not create the network.	Repeat the procedure. Check whether the network already exists.
An error occurred while editing the network. Please try again shortly.	The server did not apply the change.	Repeat the procedure.

A network cannot be deleted

If the portal reports **You cannot delete the network IP address because a mitigation is currently running.**, a running mitigation is blocking the deletion.

- ▶ End the mitigation of the network.
- ▶ Delete the network again afterwards.

The resync fails

If the portal reports **An error occurred while triggering the networks resync. Please try again shortly.**, the server did not accept the job. Repeat it after a short while; the resync can be repeated and does not change the networks themselves.

3.4 User accounts

An account cannot be added

Message	Cause	Remedy
This user already belongs to the company.	A user account already exists for this email address in the company.	Look for the account in the list. If it is to receive different rights, change the role instead of creating a second account.
Failed to add the user to the company.	The server did not create the account.	Check the email address and repeat the procedure.
This field is required.	A mandatory field is empty.	Fill in the marked field.
The value can be up to 255 characters long.	The entry is too long.	Shorten the value to 255 characters at most.
The changes couldn't be saved.	The server did not apply the change.	Repeat the procedure. Afterwards, check in the list whether the change has been applied.

The procedure is described in [Adding an account](#).

The invited person receives no email

A newly created account stays in the **Pending** state until the invited person accepts the invitation and sets a password.

- ▶ Check the spelling of the email address in the list.
- ▶ Ask the recipient to check their spam folder.
- ▶ Send the invitation again using the **Resend invitation** icon.
- The portal confirms with **The invitation has been successfully sent to the user.**

If the portal reports **The invitation couldn't be resent to the user.** instead, sending has failed. Repeat it after a short while. If the invitation link has already expired for the

recipient – recognisable by the message **The token has expired. Please restart the process.** – send the invitation again as well.

The SIEM connection cannot be established

The **SIEM Settings** tab checks the connection only when you click.

Message	Cause	Remedy
The connection couldn't be established.	The host, the port, or the API token is wrong, or the destination cannot be reached from the portal.	Check the host and the port. Enter the API token again – a stored token is only shown as (stored) and cannot be read back. Then have someone check whether a firewall is blocking the connection.
The connection could be established.	The entries are correct.	Save the settings.

Further details on the tab are given in [SIEM Settings tab](#).

3.5 Companies

A company cannot be added or edited

Message	Cause	Remedy
An error occurred while adding the company. Please try again shortly.	The server did not create the company.	Repeat the procedure. Before that, check in the list whether the company already exists.
An error occurred while editing the company. Please try again shortly.	The server did not apply the change.	Repeat the procedure.
This field is required.	A mandatory field is empty.	Fill in the marked field.
The value should be a positive number.	A numeric field contains a negative number or a zero.	Enter a positive number.

A company cannot be deleted

Message	Cause	Remedy
You cannot delete the network because a mitigation is currently running. Please end the mitigation first and try again.	A mitigation is running for one of the company's networks. Deleting the company would delete its networks as well.	End the mitigation and delete the company again afterwards.
An error occurred while deleting the company. Please try again shortly.	The server did not delete the company.	Repeat the procedure.



Deleting a company also deletes its networks, user accounts, and data permanently.

Additional contacts for notifications

An additional contact address stays **Pending** until the recipient answers the verification email. Only then does it receive notifications.

Message	Cause	Remedy
The contact could not be added.	The address was not accepted.	Check the spelling. Check whether the address is already in the list.
The verification email could not be resent.	Sending failed, or the limit has been reached.	Five verification emails per hour are allowed per contact. Wait and send again afterwards.
The contact could not be removed.	The server did not delete the contact.	Repeat the procedure.

If a contact stays **Pending** although the email was sent, the verification link has not been opened or has expired. Send the verification email again.

3.6 API access

An API token cannot be created

Message	Cause	Remedy
Must be a whole number between 1 and 90.	The validity period lies outside the permitted range.	Enter a whole number between 1 and 90 days.
This field is required.	The name of the token is missing.	Assign a name by which you will recognise the token later.
There was a problem creating the token. Please try again.	The server did not create the token.	Repeat the procedure.
There was a problem deleting the token. Please try again.	The server did not delete the token.	Repeat the procedure.



Please copy your new API token. For your security, it will not be shown again. If you did not copy the token before closing the dialog, it cannot be read back afterwards. Delete it and create a new one.

The procedure is described in [Creating an API token](#).

The API rejects a request

Response	Cause	Remedy
400 Bad Request	The request is incomplete or contains an invalid value.	The returned ViolationV0 object names the field and the reason. Correct the value and send the request again.
401 Unauthenticated	The bearer token is missing, misspelled, or expired.	Check the Authorization: Bearer <token> header. A

Response	Cause	Remedy
401 Unauthorized	The user account behind the token lacks the permission for this endpoint – or the identifier in the path does not exist or belongs to a different company. The API answers both the same way so that it does not disclose identifiers of others.	token is valid for 90 days at most; after that, create a new one.
403 Forbidden	The user account behind the token lacks the permission for this endpoint – or the identifier in the path does not exist or belongs to a different company. The API answers both the same way so that it does not disclose identifiers of others.	First check the identifier in the path, then the role of the user account.
429 Too Many Requests	240 requests per minute are allowed, counted per user account.	Spread the requests over time. Evaluate the Retry-After header of the response and repeat the request afterwards.

The complete list is given in [Possible responses to a request](#).

A SOC account gets no access with its API token

If the API rejects a request with **SOC accounts cannot access organisation-scoped data with a personal access token.**, this is not an error but a safeguard: a SOC account owns no networks of its own. Over a personal API token it would return the data of whichever company it last switched into.

- Address the company in the path explicitly: use the endpoints under `/organisations/{organisation}/...` instead of the endpoints without a company in the path.

4. Reference

4.1 Notational conventions

Formatting	Description
Text in bold	Identifies screen elements from the graphical user interface.
Links	Identifies references to chapters and sections within the manual, as well as external sources.
Text in monospace	Identifies commands, code, and input.
<ABC>	Identifies placeholders to be filled in by the customer or the system.
☑	Indicates prerequisite steps that users must fulfill before performing a procedure.
▶	Indicates steps that users should perform.
▷	Indicates subordinate steps that users should perform.
↳	Indicates the interim result for checking after one or more steps have been performed.
→	Indicates the result that should be obtained after performing several steps.
 Text	Identifies important information to support users.
 Text	Identifies particularly important information that, if not observed, can lead to incorrect settings or data loss.
 Text	Identifies examples to support users.

4.2 Glossary

Element	Description
Scrubbing	Scrubbing refers to the process of filtering Internet traffic, particularly at OSI layers 3/4, in such a way that valid clean traffic is distinguished from harmful attack traffic.
Scrubbing Center	A scrubbing center is a high-performance Internet node (point of presence/PoP) consisting of hardware, software, and broadband connectivity that is capable of performing scrubbing efficiently using Myra technology.
Myra Partner	An ISP is a Myra customer that uses the Myra product Network DDoS Protection (on-prem) and has implemented it within its own network.
End customer	An end customer is the customer of a Myra partner that uses the volumetric DDoS protection service for OSI layers 3/4 powered by Myra .
Network DDoS Protection (cloud)	Cloud scrubbing is a service provided by Myra in the form of Security-as-a-Service (SaaS) that protects the network of the Myra partner from volumetric DDoS attacks on OSI layers 3/4. Functionality: As soon as parameters defined in advance are exceeded, the (attack) traffic is briefly rerouted into a cloud scrubbing center by means of Border Gateway Protocol (BGP) rerouting and washed clean of unwanted traffic there, so that only clean traffic is forwarded to the recipient over a secured connection. Advantages: Network DDoS Protection (cloud) can reliably defend against DDoS attacks with a bandwidth of several Tbit/s. This defence bandwidth is always available to the Myra partner, even if it exceeds the total line capacity (bandwidth) of the Myra partner's own physical connection. It is irrelevant

Element	Description
	whether the entire line capacity of the Myra partner is physically implemented by one line provider or by several (multi-vendor strategy). This DDoS protection is also retained if the Myra partner changes line provider in the future or adds further ones. Restriction: For technical reasons, protection through Network DDoS Protection (cloud) is only possible for individual /24 prefixes with IPv4 and /48 prefixes with IPv6. Because of the restriction to exactly these sizes that generally applies on the public internet, networks smaller than /24 or /48 cannot be protected through cloud scrubbing.
Network DDoS Protection (on-premise)	Myra provides its partner with one or more physical scrubbing centers, which are integrated into the network infrastructure of the Myra partner. This ensures that all routers involved in routing relevant to scrubbing are controlled by Myra or the Myra partner. This also makes it possible to define valid routes for smaller prefixes (that is, networks smaller than /24 or /48) without causing problems for public routing.
Network DDoS Protection (hybrid)	Network DDoS Protection (hybrid) is a combination of the OnPrem and Cloud network DDoS protection solutions. If the bandwidth of a DDoS attack exceeds the line capacity (of one or of several physical connections) of the Myra partner, the resources of Myra can be used as a second line of defence and a switch can be made from Network DDoS Protection (on-prem) to Network DDoS Protection (cloud), in order to reliably defend against volumetric DDoS attacks on OSI layers 3/4 with bandwidths of several Tbit/s as well. This enables Myra partners to ensure that their own servers and networks, as well as those of their end customers, remain accessible even during DDoS attacks with extremely high bandwidths.
Myra Flow -	The Myra Flow Application is an application that detects DDoS attacks on the basis of the data supplied by the edge routers of the Myra partner and thresholds defined beforehand. The Flow-Monitoring reports detected attacks to downstream instances to automatically initiate countermeasures.

Element	Description
Application	The application is operated in the network infrastructure of the Myra partner, usually on a virtual machine.
Uplink	An uplink is a dedicated channel for returning the cleaned traffic to the Myra partner after scrubbing has been completed. This channel is necessary to avoid a routing loop. Uplinks can be set up redundantly as direct connect (physical) or as VLAN, IPsec, GRE (virtual).
On Demand	On demand means that traffic filtering is only activated once an attack exceeds the specified thresholds. Normally, traffic does not flow through the scrubbing center. With automatic attack detection, routing is changed and data traffic is processed there. After 24 hours, regular routing is restored – a period recommended by Myra to prevent unnecessary route flapping.
Route flapping	Route flapping refers to the state of different announced routes on the internet at the same time. This is dangerous and has far-reaching negative consequences for routing on the public Internet.
Myra App	The Myra App is a web-based user interface for controlling and configuring the protection systems.
Myra Data Hub	The Myra DataHub is a web-based user interface (WebGUI) for Myra partners to view an overview of end customers. This shows the end customers with the connected networks and their created accounts. Within this WebGUI, end customers have an overview of traffic history, the networks that have been activated, and the mitigation reports that have been collected. Within the traffic history view, it is possible to filter between bandwidth and packet rate, sorted by destination IP, overview of source countries, ASN, and packet rates by port. In addition, various viewing periods of up to 24 hours can be defined. The set thresholds can also be viewed via the WebGUI. In addition, the functionality of the Myra DataHub includes the option of initiating manual mitigation and configuring the defined companies, networks, and users by the Myra partner.